

BigFix® Remote Control Installation Guide

Special notice

Before using this information and the product it supports, read the information in Notices.

Edition notice

This edition applies to version 9.5 of BigFix and to all subsequent releases and modifications until otherwise indicated in new editions.

Contents

- Chapter 1. BigFix® Remote Control V9.1.2V9.1.3V9.1.4 Installation Guide..... 1**
 - Audience..... 1
 - Versions..... 1
 - Terms used in this guide..... 1
- Chapter 2. Overview of the BigFix® Remote Control system..... 3**
 - How to use the guide..... 5
 - BigFix® Remote Control operating requirements..... 6
 - A Basic installation..... 6
 - Installation with support for firewall and NAT traversal..... 8
 - Installation with support for remote control sessions over the internet..... 9
 - Server requirements..... 9
 - Server environment guidelines..... 11
 - Controller requirements..... 16
 - Target requirements..... 16
 - Gateway requirements..... 18
 - Broker requirements..... 19
- Chapter 3. Get started..... 21**
- Chapter 4. Install the BigFix® Remote Control components..... 22**
 - Obtain the installation files..... 22
 - Install the server..... 25
 - Set up the database..... 25
 - Installing by using the server installer..... 32
 - Installing on WebSphere® Application Server version 8.5: deploying the war file..... 44
 - Installing from the BigFix® console..... 57
 - Install the target..... 57
 - Installing the Windows™ target..... 57
 - Installing the Linux™ target..... 81

Install the BigFix® Remote Control Target for macOS.....	82
Run a target custom installation.....	84
Installing the target by using the SPB file.....	95
Install the controller.....	95
Installing the controller on a Windows™ system.....	96
Installing the Linux™ controller.....	96
Install the BigFix® Remote Control Controller for macOS.....	97
Installing the controller in other supported operating systems.....	99
Installing a preconfigured controller component.....	99
Install the command-line tools.....	103
Installing the cli tools on a Windows system.....	103
Installing the CLI tools in Linux™	105
Install gateway support.....	106
Installing Windows gateway support.....	106
Installing Linux™ gateway support.....	107
Install broker support.....	108
Installing Windows broker support.....	108
Installing Linux broker support.....	109
Chapter 5. Utility for extracting the component installation files.....	111
Extract the installation files by using the additional setup utility.....	112
Chapter 6. Enable secure target registration.....	114
Enable secure target authentication in the server.....	114
Enabling secure registration when you install the server.....	114
Enabling secure target registration after you install the server.....	115
Add a token for secure target registration.....	115
Adding a token on a Windows system.....	117
Add a token on a Linux system.....	119
Chapter 7. Install the driver for smart card authentication.....	121
Installing the virtual smart card reader driver by using the installer.....	121

Adding or removing the smart card reader driver by using the installer.....	122
Installing the smart card reader driver by running a silent installation.....	123
Installing the virtual smart card reader driver when you upgrade the target.....	123
Installing the driver and certificate by using a Fixlet.....	124
Installing the certificates by using a Fixlet.....	125
Downloading the certificates.....	125
Chapter 8. Manage the component services.....	127
Starting, stopping, or restarting the Windows™ components.....	127
Starting, stopping, or restarting the Linux™ components.....	127
Chapter 9. Enabling email.....	129
Chapter 10. Configure LDAP.....	130
Setting up LDAP synchronization.....	130
Verifying connection information.....	132
Configuring connection credentials.....	133
Setting connection security.....	135
SASL (Simple Authentication and Security Layer).....	136
SSL (Secure Socket Layer).....	137
Setting user authentication properties.....	137
Authenticating the user.....	137
Searching for the users directory entry.....	139
Importing Active Directory Groups.....	141
Testing the Connection.....	143
Verifying that the groups are imported.....	145
Sample LDAP Configuration File.....	145
Chapter 11. Federal information processing standard (FIPS 140-2) compliance in BigFix® Remote Control.....	150
Enable FIPS compliance on the server.....	153
Enabling FIPS compliance on a server installation with a stand-alone WebSphere Application Server.....	153

Enabling FIPS compliance on an automated server installation.....	154
Enabling FIPS compliance on the controller.....	156
Enable FIPS compliance on the target.....	159
Enabling FIPS compliance on a Windows™ target.....	159
Enabling FIPS compliance in Linux® or UNIX® based operating systems.....	160
Enabling FIPS compliance on the gateway.....	161
Enabling FIPS compliance on the broker.....	161
Chapter 12. NIST SP800-131A compliance in BigFix® Remote Control.....	163
Enable NIST SP800-131A compliance on the server.....	164
Enabling NIST SP800-131A compliance during the server installation.....	164
Enabling NIST SP800-131A compliance on a server with a stand-alone WebSphere Application Server.....	164
Enabling NIST SP800-131A compliance after you install the server.....	165
Creating a certificate for an MS SQL database when NIST SP800-131A is enabled.....	168
Enabling NIST SP800-131A compliance on the controller.....	171
Enabling NIST SP800-131A compliance in the stand-alone controller.....	172
Enable NIST SP800-131A compliance on the target.....	172
Enabling NIST SP800-131A compliance in a Windows® target.....	173
Enabling NIST SP800-131A compliance on Linux® or UNIX® based targets.....	174
Enabling NIST SP800-131A compliance on the gateway.....	174
Enabling NIST SP800-131A compliance on the broker.....	175
Enabling NIST SP800-131A compliance on the CLI tools.....	176
Enabling NIST SP800-131A compliance when you install the Windows cli tools.....	176
Enabling NIST SP800-131A compliance on the cli on Linux® or UNIX® based targets.....	176
Chapter 13. Verifying the server installation.....	177
Chapter 14. Recover from installation errors.....	178
Recovery steps.....	178
Errors during installation.....	178
Not enough memory.....	179

DB2® connection error when database options are verified.....	179
Oracle pre-checks.....	180
libstdc++.so.5 error when installing the server using the installation program.....	180
Errors after installation.....	181
Out of memory error.....	181
Database connection authorization failure.....	183
Application welcome page does not display.....	184
DB2® connection error when database options are verified.....	184
Targets cannot contact the server.....	185
Errors when you use Oracle as the database.....	187
Errors when trying to connect to the Microsoft® SQL database in FIPS compliancy mode.....	187
Chapter 15. Uninstall the components.....	188
Uninstall the server.....	188
Uninstalling the server by using the installer.....	188
Uninstalling the server application in IBM® Websphere Application Server.....	188
Uninstalling the server using Add or Remove programs.....	189
Uninstalling the target on Windows™ systems.....	189
Uninstalling the target on Linux® systems.....	190
Chapter 16. Upgrade from previous versions.....	191
Upgrade the gateway component.....	191
Upgrade the broker component.....	191
Upgrade the server component.....	192
Upgrade the target component.....	193
Upgrade the controller component.....	194
Chapter 17. Maintaining the target installation.....	195
Appendix A. Properties that can be set in the target configuration.....	196
Appendix B. Support.....	223
Notices.....	224
Index.....	a

Chapter 1. BigFix Remote Control

V9.1.2V9.1.3V9.1.4 Installation Guide

By using BigFix® Remote Control you can remotely support and control thousands of PCs and servers, on an enterprise scale, from a central location or directly, in peer to peer mode.

Use the BigFix Remote Control administration web interface, to view and control a remote desktop, including its keyboard and mouse, anywhere on your network. You can also chat, transfer files, remotely guide the users, administer the policies to be applied to different users and target groups, and much more. These features can help provide more efficient and effective analysis of user problems from the administrators desktop, without the added cost of dispatching a technician or relying on user descriptions over the phone. Use BigFix Remote Control to deliver better support, more flexibility, and richer security, by using robust features that include enhanced central logging and video capture of the sessions and full data stream encryption.

Audience

This guide is for administrators and IT managers who want to install and administer BigFix Remote Control. It details the system requirements for each of the components and provides installation instructions that allow you to deploy the program in your environment. It also includes information about configuring and maintaining BigFix Remote Control.

Versions

The guide includes the functions introduced in BigFix Remote Control V9.1.3V9.1.4, © Copyright HCL Ltd. 20012020.

Terms used in this guide

The following terms are all BigFix Remote Control terms, but are used throughout the guide without being labeled every time with BigFix Remote Control:

- Controller always means BigFix Remote Control Controller application
- Target always means BigFix Remote Control Target
- Server always means BigFix Remote Control Server
- Broker always means BigFix Remote Control Broker

- Managed mode refers to installations where a server has been deployed and the targets are configured to register and report status to the server.

Chapter 2. Overview of the BigFix Remote Control system

The BigFix Remote Control system includes the following main components:

BigFix Remote Control Target

The target is installed on every computer that you want to control remotely with BigFix Remote Control. It listens for connection requests that come from the controller. You can also start a remote control session over the internet with a target, by using a broker.

Targets that are outside of your intranet can be configured to register their details with the server. Sessions with these targets are managed by server policies. The targets must be deployed with the **Managed** property set to Yes. The **ServerURL** and **BrokerList** properties must also be configured. Targets can also be configured so that they do not send their details to the server. These targets are classed as unregistered targets. You can install the target software and set the **Managed** property to *No*. The **BrokerList** property must also be set. You can also use the on-demand target features to start a remote control session with a computer that does not have any target software preinstalled. Server policies are used to manage the on-demand sessions. The target software is deleted at the end of the session. For information about target requirements, see [Target requirements \(on page 16\)](#).


BigFix Remote Control Controller

The controller can be installed by using the Fixlet, or by using the installer that is provided for use in peer-to-peer sessions. It can also be launched in context from the remote control server or the BigFix Remote Control console. In all instances, the controller can be used to allow the user to control a remote computer on which the remote control target is installed. The controller delivers an interface to several actions, available to the controller user, like remote control, guidance, chat, file transfer, collaboration, and many more. For information about controller requirements, see [Controller requirements \(on page 16\)](#).

BigFix Remote Control Server

A web application that manages all the deployed targets that are configured for managed mode and to point to the BigFix Remote Control Server 's URL. You can deploy it on an existing WebSphere® server, or install it by using the installer package along with an embedded version of WebSphere. The server listens for HTTP or HTTPS connections by default. When it is installed with the embedded WebSphere option, WebSphere it listens on ports 80 and 443. When it is deployed on top of an existing WebSphere server, the BigFix Remote Control server listens on ports 9080 and 9443. The server requires a database

server: embedded Derby, only for proof of concept deployments; DB2®, SQL Server, and Oracle are the supported options. Additionally, it can also be configured to synchronize and authenticate user and group data from an LDAPv3 server, such as Active Directory or Tivoli Directory Server. This deployment scenario has the same networking characteristics as peer-to-peer. Therefore, direct TCP connectivity is required between all the controllers and all the targets. However, the BigFix Remote Control server provides a method of centralized, and finer, policy control, where targets can have different policies that are determined by the user who is trying to start the remote control session. The Server also provides for centralized audit and storage of full session automatic recordings. In this scenario, the controller is not a stand-alone application, but is started as a Java™ Web Start application from the BigFix Remote Control server's web interface to start the remote control session.

 **Note:** Peer-to-peer and managed are not exclusive modes. You can configure the BigFix Remote Control target in the following ways:

- To be strictly managed.
- To fail back to peer-to-peer mode when the server is not reachable.
- To accept both peer-to-peer and managed remote control sessions.

The following components can be used only in managed mode:

BigFix Remote Control CLI tools

CLI tools are always installed as part of the target component but you can also install them separately. The CLI provides command-line tools for the following tasks:

- Script or integrate the launch of managed remote control sessions.
- Run remote commands on computers with the managed target installed.

BigFix Remote Control Gateway

A service that is installed in computers in secure network boundaries, where there is strict control of traffic flows between the secure networks. For example, the firewall at the boundary allows only traffic between a pair of specific IP address and ports. In these scenarios, a network of gateways can be deployed. The gateway routes and tunnels the remote control traffic from the controller, which is located in a particular network zone, to the target that is in a different network zone. The gateway is a native service that can be installed on a computer that has a Windows™ or Linux™ operating system installed. It does not have a default port for listening, although 8881 is a usual choice, and can be configured for multiple incoming listening ports and outgoing connections.

BigFix Remote Control Broker

A service that is installed in computers typically in a DMZ so that computers outside the enterprise network, in an Internet cafe or at home, can reach it. The BigFix Remote Control broker receives inbound connections from the controller and the target and tunnels the remote control session data between the two components. The broker is a native service that can be installed on a Windows or a Linux computer. It does not have a default port for listening, but 443 is a recommended option because usually this port is open for outbound connections and has fewer issues with content filtering than, for example, 80 would have.

How to use the guide

The process of getting BigFix Remote Control up and running varies, depending on your network environment and the management granularity you want to achieve. The installation guide focuses on three types of deployments:

Peer to peer

Is the simplest scenario and therefore ideal for small deployments. All targets are in network sight of the controllers and there is no requirement to centrally manage the controller policies.

Intranet managed

Are most appropriate in a complex network infrastructure that requires the deployment of gateways to traverse firewalls, or there is a requirement for strict policy control and centralized auditing.

Managed

With support for internet sessions where at least one broker must be installed in an internet-facing computer so that it is visible to targets outside the controller's network sight.

For the sake of readability and generality, the installation guide assumes the following restrictions:

- Each BigFix Remote Control server must have access to one of the supported database servers. The database can be located locally on the server computer or remotely on a separate server. The supported database systems are DB2, Oracle, and MS SQL. It is also possible to install the server by using the embedded Derby database that is provided by the installer. However, this configuration is not supported for production deployments.
- In managed environments, each controller can make an HTTP or HTTPS connection to the BigFix Remote Control server.

- In managed environments, each BigFix Remote Control target computer in the network must be able to make an HTTP or HTTPS connection to a server, a gateway, or a broker on the specified ports.

If your network configuration does not match any of the scenarios in that chapter, contact a support technician for more options.

The initial deployment of a minimal managed BigFix Remote Control system (server and a few targets) can take approximately 1 hour to complete.

Several steps in the BigFix Remote Control installation depend on the completion of prior steps. For this reason, it is recommended that you follow the guide in the order presented.

BigFix Remote Control operating requirements

BigFix Remote Control runs efficiently by using minimal server, network, and client resources. The requirements for the client programs are not stringent. The hardware that is required by the server and the target depends on the number of computers that are administered and the frequency that is defined for their status updates.

A Basic installation

The most basic installation requires the BigFix Remote Control target and controller components. Use the two components to start a peer to peer remote control session, for which the policies are defined only at target level.

The port to be used for target to controller communication is configurable at installation time. The default is port 888.

Such an installation provides basic audit information. This information is accessible from the BigFix console. It is also stored in the application event log, in a Windows operating system, or system log, in a Linux operating system. However, if centralized auditing and management of users and computers is required, install the server component.


The server component provides a single interface where controller users can easily search for targets. They can also organize the targets that are most frequently accessed and view their session history. For an administrator, a managed environment provides the following extra capability.

- Centralized management of users and targets: Users can be organized into groups with similar profiles. They can be organized manually, by using the BigFix Remote Control server interface, or by importing users and groups from LDAP. Similarly, targets can be organized into groups manually or

by setting target membership rules to automatically assign a target to a specific group. For more information about target membership rules, see the *BigFix Remote Control Administrator's Guide*.

- Centralized policy management: When a session is started from the server interface, the permissions that are set for the session are derived from the target and controller properties. Provides more flexibility to define different levels of access, against a single target, for different users in your organization.
- Centralized auditing and recording repository: Administrators can use the BigFix Remote Control server interface to browse and examine audit information. They can also view recordings that are associated with a specific remote control session. Administrators can search the existing session history. For example, by user ID or computer name.
- Access request management: Administrators can grant temporary access, or increase the level of access, to a target or group of targets. Temporary access can be granted to BigFix Remote Control registered and unregistered users.
- Reporting capabilities

Figure 1. Basic installation environment




Note: It is not necessary to install the controller component in a managed environment. Remote control sessions are launched in-context from the BigFix Remote Control server interface. You can also

configure the target components, in a managed environment, to accept peer to peer remote control requests from a stand-alone controller component. For more information about installing the target, see [Install the target \(on page 57\)](#).

Installation with support for firewall and NAT traversal

In some environments, it is not possible to open a port in a firewall to enable controller to target, or target to server communication for all endpoints. It is more appropriate to enable traffic from, or traffic to a single computer that acts as a gateway to traverse the firewall.

The gateway component can be strategically installed in your network to enable traffic between targets and controllers, or targets and servers that are in different networks. This component can also be used as a proxy server to forward the target's status update to the remote control server.




Installation with support for remote control sessions over the internet

Sometimes the target that requires support is out of network sight in an internet location. For example, in a hotel or an airport lounge.

Use the broker component to enable remote control sessions to these computers by bridging the target and controller communication. The broker must be placed in the DMZ and a gateway is required to provide secure communication to the server in the intranet.

In this scenario, the controller user can start a broker connection and obtain a connection code from the server. The user who requires assistance enters the connection code by using the appropriate menu option in the target UI. When the session details are validated by the server, the session is connected.


Figure 2. Sample deployment environment



Server requirements

The hardware that is required by the server component depends on the number of computers that are administered and the frequency that is defined for their status updates.

The distributed architecture of BigFix Remote Control allows a single server to support hundreds of thousands of computers.

 **Note:** BigFix Remote Control includes entitlement for DB2 v10.5 and WebSphere v8.5.

The computer on which you install the BigFix Remote Control server must have the minimum following items or capability:

1. 1 Quad core or two dual core processors. 2.40 GHz with supported OS.
2. A minimum of 4 GB of memory.
3. A minimum of 2 GB of storage or hard disk space to install, and an average of 2 MB per client in the database.
4. A minimum screen resolution of 800 by 600 pixels is required when you run an automated server installation.
5. Adequate space for storing session video recordings. Recordings are stored on the hard disk and their size can vary depending on the duration and screen activity of the session. On average a 5-minute session, 8-bits mode, can use about 2 MB of space. In true color 24-bit mode, recordings can take more space.
6. A network card that supports TCP/IP.
7. A supported browser.


Operating system support

The following operating systems are supported.

- Windows Server 2008.
- Windows Server 2008 R2.
- Windows Server 2012.
- Windows Server 2012 R2.
- Windows Server 2016.
- Red Hat Enterprise Linux 5.0 or later.
- Red Hat Enterprise Linux 6.0 or later.
- Red Hat Enterprise Linux 7.0 or later.
- SUSE Linux Enterprise Server 10 or later.
- SUSE Linux Enterprise Server 11 or later.
- CentOS 5.0 or later.
- CentOS 6.0 or later.

Supported Architectures

- Intel™ IA®-32 (also known as x86, x86-32)
- Intel 64 or AMD64 (also known as x64, x86-64, EM64T)

 **Note:** IA-64 (also known as Itanium™) processors are not supported.

The following databases are supported.

- IBM DB2 10.x, 11.x Workgroup(WSE) and Enterprise Edition(ESE).
- Oracle 11g and 12c.

When you use an Oracle database, if you are using the Oracle 11g drivers, set `oracle.increment.keys.off=1` in the `trc.properties` file. Restart the server service.


- Microsoft SQL server 2008, 2012, 2014, and 2016.

You must use a JDBC driver whose version is bigger than 6.3. Older versions do not support TLS1.2 or JRE8.

When you use an MS SQL database, Windows authentication is not supported. You cannot log on with a domain user. You must use mixed mode authentication and create an SQL user to connect to the database.

 **Note:** You should use JDBC drivers which support at least Java 8.

Derby Version 10.13 is included with the BigFix Remote Control server and is installed locally when you select the Derby option during the installation.

 **Note:** Install Derby only for proof of concept configurations. Derby is not supported in production environments.


When you install the server by using the installer, a WebSphere Application Server Liberty Profile version 18.x.x.x is also installed.


Server environment guidelines

In addition to system requirements, you must also determine which type of server installation to use in your environment. Use the following information as a guide.

Table 1. BigFix Remote Control server installation types

Server installation type	Components installed	Install by using the BigFix console	Install by using the installation files
1	Embedded Liberty profile. Embedded Derby database.	Yes	Yes
2	Embedded Liberty profile, that uses an already installed DB2, MS SQL, or Oracle database	Yes	Yes
3	Stand-alone BigFix Remote Control server that accesses WebSphere Application Server, by using an already installed DB2, MS SQL, or Oracle database	No	Yes

 **Note:** Server installation types 1 and 2 are available only when you use Windows or Linux operating systems.

 **Note:** Server installation type 1 must be used only in Proof of Concept or test deployments.

The following sections provide guidance and recommendations based on environment size.

Small environment guidelines


For environments containing up to 5K targets, you can use server installation types 1, proof of concept only, or 2 in [Server environment guidelines \(on page 11\)](#).


Also, consider the following extra requirements.

- Processors: 1 Quad core or 2 dual core processors, 2.40 GHz, with supported OS.
- Memory: 4 GB RAM.
- Storage. For more information, see [Server requirements \(on page 9\)](#).
- Heartbeat configuration

Table 2. Heartbeat configuration properties: suggested values for a small environment

Property in <code>trc.properties</code>	Value
heartbeat.timeout	60

Property in <code>tr-c.properties</code>	Value
	<p> Note: If there are performance issues, set the value to 1440, which is 24 hours. For example, when there is heavy usage of reports, especially with Derby.</p> <p>Default is 60, which is 1 hour.</p>
heartbeat.retry	10
heartbeat.delay	20
heartbeat.on.wake	0
heartbeat.on.user.change	1
heartbeat.on.change	0
heartbeat.on.stop	0

 **Note:** Installation type 1 is suitable for demonstrations or pilot projects. Installation type 2 can give better performance, which might be preferred for production systems in these environments.

Medium environment guidelines




For environments containing from 5K to 75K targets, you can use server installation types 2 or 3 in [Server environment guidelines \(on page 11\)](#). In terms of performance, installation type 2 is suitable. However, with installation type 3 you can also use the admin functions of the installed WebSphere Application Server.


Also, consider the following extra requirements.

- Processors: 1 Quad core or 2 dual core processors, 2.40 GHz.
- Memory: 8 GB RAM.
- Storage: RAID 5 - 6 HDD. DB2, Oracle, or MS SQL 64 bit or 32 bit.
- Heartbeat configuration -

Table 3. Heartbeat configuration properties: suggested values for a medium environment

Property in <code>tr-c.properties</code>	Value
heartbeat.timeout	1440

Property in <code>tr-c.properties</code>	Value
	<p> Note: If there are specific groups of computers where more regular updates are needed, a smaller heartbeat timeout setting can be applied as a group attribute for those specific groups of targets. For details of setting this attribute at group level, see the chapter that explains how to create a target group in the <i>BigFix Remote Control Administrator's Guide</i>.</p>
heartbeat.retry	10
	<p> Note: In an environment that contains target numbers nearer to 75 K, set this value to 20 to help with performance.</p>
heartbeat.delay	20
	<p> Note: In an environment that contains target numbers nearer to 75 K, set this value to 40 to help with performance.</p>
heartbeat.on.wake	0
heartbeat.on.user.change	1
heartbeat.on.change	0
heartbeat.on.stop	0

 **Note:** In this type of environment, ensure that the target deployment is done in stages. A staged deployment can avoid overload in the server when the targets try to register with the server. Give the **RegistrationDelay** target property a value that distributes the target computer registration evenly through the staged deployment. Distribute the target registration to avoid too many computers trying to register at the one time.

Large environment guidelines




For environments containing from 75K to 225K targets, you can use server installation type 3 in [Server environment guidelines \(on page 11\)](#).

Also, consider the following extra requirements.

To host WebSphere Application Server

- Processors: 2 Quad core processors. 2.40 GHz with supported OS.
- Memory: 16 GB RAM.
- Storage: RAID 5 - 6 HDD.
- Heartbeat configuration -


Table 4. Heartbeat configuration properties: suggested values for a large environment

Property in <code>tr-c.properties</code>	Value
heartbeat.timeout	1440
	<p> Note: If there are specific groups of computers where more regular updates are needed, a smaller heartbeat timeout setting can be applied as a group attribute for those specific groups of targets. For details of setting this attribute at group level, see the chapter that explains how to create a target group in the <i>BigFix Remote Control Administrator's Guide</i>.</p>
heartbeat.retry	60
	<p> Note: In an environment that contains target numbers nearer to 75 K, set to a higher value to help with performance.</p>
heartbeat.delay	60
	<p> Note: In an environment that contains target numbers nearer to 75 K, set to a higher value to help with performance.</p>
heartbeat.on.wake	0
heartbeat.on.user.change	1
heartbeat.on.change	0
heartbeat.on.stop	0

- Optional: 2 network cards, one for target communications and one for database communications that could aid in performance tuning.


To host the database, DB2, Oracle, or MS SQL supported.


- Processors: 4 Quad core processors, 2.40 GHz.
- Memory: As recommended by the database supplier.
- Storage: RAID 5 - 6 HDD 146 GB

 **Note:** The database administrator must tune the database for appropriate performance.

The following guidelines must also be considered when you use large reports, as some performance degradation can be experienced.

- Ensure that the **All targets** report is not the default home page report.
- Ensure staged deployment of the targets to avoid overload in the server when they try to register.


 **Note:** Give the **RegistrationDelay** target property a value that distributes the target computer registration evenly through the staged deployment. Distribute the target registration to avoid too many computers trying to register at the one time.

 **Note:** If you configure LDAP and LDAP synchronization is enabled, set a reasonable frequency for the synchronization. If your LDAP configuration is set up to import many users and groups, set the frequency to 24 hours. For more information about configuring LDAP, see [Configure LDAP \(on page 130\)](#).


Controller requirements

The Controller is a Java based application that can run on any operating system with the following prerequisites:

- Java Run Time environment: Oracle 8 or IBM® 8 Oracle Java SE Runtime Environment 8 or IBM Java SE Runtime Environment 8.

 **Note:** Oracle Java is not supported in FIPS or NIST SP800-131a mode. You must use the IBM Java in this mode.

- Web Browser: either Microsoft™ Internet Explorer 9, 10, 11 or Mozilla Firefox Extended Support Release (ESR) 24, 31.
- Web Browser:
 - Microsoft Internet Explorer 9, 10, 11.
 - Mozilla Firefox Extended Support Release (ESR) 45.
 - Safari 10 on OS X 10.11 El Capitan or macOS 10.12 Sierra.
- Java Run Time environment: Sun 1.6, Oracle 1.6, 1.7 or IBM® 1.5, 1.6, 1.7

 **Note:** Sun Java and Oracle Java are not supported in FIPS or NIST SP800-131a mode. You must use the IBM Java in this mode.

- Web Browser: either Microsoft Internet Explorer 9, 10, 11 or Mozilla Firefox ESR 24, 31.

Target requirements

The computer on which you install the BigFix Remote Control target must have the minimum following items or specification:

- At least a 1 GHz Intel® or AMD processor.
- A minimum of 1 gigabyte (GB) RAM (32-bit) or 2 GB RAM (64-bit).
- A minimum of 50 MB hard disk space.
- Adequate space for storing session video recordings. Recordings are stored on the hard disk and their size can vary depending on the duration and screen activity of the session. On average a 5-minute session, 8-bits mode, can use about 2 MB of space. In true color 24-bit mode, recordings can take more space.
- The maximum display resolution per display is 7680 pixels by 4320 pixels.
- The maximum number of displays is 8 by 8.

Operating system Support


The following operating systems are supported

- Windows 7.
- Windows 8 and 8.1.
- Windows 10.
- Windows Server 2003.
- Windows Server 2003 R2.
- Windows Server 2008.
- Windows Server 2008 R2.
- Windows Server 2012.
- Windows Server 2012 R2.
- Windows Server 2016.
- Windows XP Pro (32 bits), (64 bits).
- Red Hat Enterprise Linux 5.0 or later.
- Red Hat Enterprise Linux 6.0 or later.
- Red Hat Enterprise Linux 7.0 or later.
- SUSE Linux Enterprise Server 10 or later.
- SUSE Linux Enterprise Server 11 or later.
- SUSE Linux Enterprise Desktop 10 or later.
- SUSE Linux Enterprise Desktop 11 or later.
- CentOS 5.0 or later.
- CentOS 6.0 or later.

- OS X 10.11 El Capitan.
- macOS 10.12 Sierra.
- macOS 10.14 Mojave.

Supported Architectures

- Intel IA-32 (also known as x86, x86-32)
- Intel 64 or AMD64 (also known as x64, x86-64, EM64T)

 **Note:** IA-64 (also known as Itanium) processors are not supported.

Gateway requirements

The computer on which you install the BigFix Remote Control gateway must have the minimum following items or specification:

1. At least a 1 GHz Intel® or AMD processor.
2. A minimum of 1 gigabyte (GB) RAM (32-bit) or 2 GB RAM (64-bit)
3. A minimum of 50 MB hard disk space.


Operating system support

The following operating systems are supported.

- Windows Server 2003.
- Windows Server 2003 R2.
- Windows Server 2008.
- Windows Server 2008 R2.
- Windows Server 2012.
- Windows Server 2012 R2.
- Red Hat Enterprise Linux 5.0 or later.
- Red Hat Enterprise Linux 6.0 or later.
- Red Hat Enterprise Linux 7.0 or later.
- SUSE Enterprise Linux Server 10 or later.
- SUSE Enterprise Linux Server 11 or later.
- SUSE Linux Enterprise Desktop 10 or later.
- SUSE Linux Enterprise Desktop 11 or later.
- CentOS 5.0 or later.
- CentOS 6.0 or later.

Supported Architectures

- Intel IA-32 (also known as x86, x86-32)
- Intel 64 or AMD64 (also known as x64, x86-64, EM64T)

 **Note:** IA-64 (also known as Itanium) processors are not supported.

Broker requirements

The computer on which you install the BigFix Remote Control broker must have the minimum following items or specification:

1. At least a 1 GHz Intel® or AMD processor.
2. A minimum of 1 gigabyte (GB) RAM (32-bit) or 2 GB RAM (64-bit)
3. A minimum of 50 MB hard disk space.
4. Adequate space for storing session video recordings. Recordings are stored temporarily on the hard disk and their size can vary depending on the duration and screen activity of the session. On average a 5-minutes session, 8-bits mode, can use about 2 MB of space. In true color 24-bit mode, recordings can take more space.


Operating system support

The following operating systems are supported

- Windows Server 2003.
- Windows Server 2003 R2.
- Windows Server 2008.
- Windows Server 2008 R2.
- Windows Server 2012.
- Windows Server 2012 R2.
- Red Hat Enterprise Linux 5.0 or later.
- Red Hat Enterprise Linux 6.0 or later.
- Red Hat Enterprise Linux 7.0 or later.
- SUSE Linux Enterprise Server 10 or later.
- SUSE Linux Enterprise Server 11 or later.
- CentOS 5.0 or later.
- CentOS 6.0 or later.

Supported Architectures

- Intel IA-32 (also known as x86, x86-32)
- Intel 64 or AMD64 (also known as x64, x86-64, EM64T)

 **Note:** IA-64 (also known as Itanium) processors are not supported.

Chapter 3. Get started

Now that you understand the terms and components available in BigFix Remote Control, you can identify which components you need to install:

Table 5. Determining which components to install

Requirements	Target	Controller	Server	Gateway	Broker
I want others to remotely connect to this computer.	Yes	Yes			
I want to remotely connect to other computers by using the BigFix Remote Control console or by starting the stand-alone controller.	Yes	Yes			
To centrally manage users and targets, and their policies.	Yes	Optional *	Yes		
To maintain a central audit and recording repository.	Yes	Optional *	Yes		
Traverse firewalls in your company infrastructure	Yes	Optional *	Yes	Yes	
Connect to targets outside your company network.	Yes	Optional *	Yes	Yes **	Yes

* In a managed environment, the controller user starts remote control sessions from the BigFix Remote Control server interface. Starting sessions this way does not require the controller component to be installed separately. The BigFix Remote Control server interface starts a Java Web Start controller console, in context.

** A gateway is not strictly required in a broker deployment but it does increase security.

Chapter 4. Install the BigFix Remote Control components

The BigFix Remote Control components can be installed in two ways. If you have access to the BigFix console, use a deployment fixlet to install the components.

For more information, see the *BigFix Remote Control Console User's Guide*. Alternatively use the component installation files.

You can obtain the installation files in various ways. Choose the appropriate method for obtaining the files. There is no specific order in which the different components must be installed.

Obtain the installation files

The installation files for installing the BigFix Remote Control components can be obtained in various ways.

HCL License & Delivery Portal

To install the BigFix Remote Control components, use the following images from Flexnet Operations – [HCL License & Delivery Portal](#).

Table 6. Parts required for installing BigFix Remote Control

Part number	File name
Windows operating system	<code>BIGFIX_REM_CNTRL_V913_Image_-</code>
CNEJ8ML - BIGFIX REM CNTRL V9.1.3 IMAGE1.	<code>1.zip</code>
Linux operating system	<code>BIGFIX_REM_CNTRL_V913_Image_-</code>
CNEJ9ML - BIGFIX REM CNTRL V9.1.3 IMAGE2.	<code>2.tar</code>
Windows, Linux, AIX®, Solaris operating systems	<code>BIGFIX_REM_CNTRL_V913_Image_-</code>
CNEK0ML - BIGFIX REM CNTRL V9.1.3 IMAGE3.	<code>3.tar</code>

Depending on the operating system, and the component that you are installing, determines which image file you require.

`BIGFIX_REM_CNTRL_V913_Image_1.zip`

Extract the installation files for the Windows operating system components from this image file. The Windows operating system executable files are in the `\windows` directory.

BIGFIX_REM_CNTRL_V913_Image_2.tar

Extract the installation file for the Linux server component from this image file. The `trc_server_setup.bin` file is in the `\linux` directory. Use the `BIGFIX_REM_CNTRL_V913_Image_3.tar` file to access the installation files for the other Linux components.

BIGFIX_REM_CNTRL_V913_Image_3.tar

Extract the data from the `BigFix_Rem_Cntrl_V913_Image_3.tar` file. Extract the additional setup utility files, `trc_additional_setup.exe`, and `trc_additional_setup.bin` from this image file. Use the files to extract the installation files for Windows, Linux, and other supported operating system components. Go to the `\Disk1\InstData\platform\VM` directory where `platform` is relevant to your operating system. For more information about running the additional setup utility, see [Extract the installation files by using the additional setup utility \(on page 112\)](#).

HCL License & Delivery Portal

To install the BigFix Remote Control components, use the following images from Flexnet Operations – [HCL License & Delivery Portal](#). For more information, refer to the article at https://hclpnpsupport.service-now.com/csm?id=kb_article&sysparm_article=KB0010149

Note:

IBM Passport Advantage® and Fix Central® have been replaced by FlexNet Operations®.

Table 7. Parts that are required for installing BigFix Remote Control

Part number	File name
Windows operating system	<code>BIGFIX_REM_CNTRL_V914_Image_1.zip</code>
CNJ05ML - BIGFIX REM CNTRL V9.1.4 IMAGE1.	
Linux operating system	<code>BIGFIX_REM_CNTRL_V914_Image_2.tar</code>
CNJ06ML - BIGFIX REM CNTRL V9.1.4 IMAGE2.	
Windows, Linux, macOS, AIX, Solaris operating systems	<code>BIGFIX_REM_CNTRL_V914_Image_3.tar</code>

Part number	File name
CNJ07ML - BIGFIX REM CNTRL V9.1.4 IMAGE3.	

Depending on the operating system, and the component that you are installing, determines which image file you require.

BIGFIX_REM_CNTRL_V914_Image_1.zip

Extract the installation files for the Windows operating system components from this image file. The Windows operating system executable files are in the `\windows` directory.

BIGFIX_REM_CNTRL_V914_Image_2.tar

Extract the installation file for the Linux server component from this image file. The `trc_server_setup.bin` file is in the `\linux` directory. Use the `BIGFIX_REM_CNTRL_V914_Image_3.tar` file to access the installation files for the other Linux components.

BIGFIX_REM_CNTRL_V914_Image_3.tar

Extract the data from the `BigFix_Rem_Cntrl_V914_Image_3.tar` file. Extract the additional setup utility files, `trc_additional_setup.exe`, and `trc_additional_setup.bin` from this image file. Use the files to extract the installation files for Windows, Linux, and other supported operating system components. Go to the `\Disk1\InstData\platform\VM` directory where *platform* is relevant to your operating system. The additional setup utility can be run only on Windows and Linux systems. To extract the installation files for macOS components, run the utility on a Windows or Linux system then copy the `.pkg` files to the macOS system. For more information about running the additional setup utility, see [Extract the installation files by using the additional setup utility \(on page 112\)](#).

Accessing the installation files on the installation DVD

The installation DVD contains the installation files that are required for installing the components.

Windows installation files

Go to the `\trc\windows` directory to access the required component installation file.

Linux server component

Go to the `\trc\linux` directory to access the `trc_server.bin` file, for installing the server. For all other component installation files, go to the `\Disk1\InstData\platform\VM` directory where *platform* is relevant to your operating system. Use the additional setup utility files `trc_additional_setup.exe` or

`trc_additional_setup.bin` to extract the required installation files. For more information about running the additional setup utility, see [Extract the installation files by using the additional setup utility \(on page 112\)](#).

Downloading the files from the server UI

If you install the BigFix Remote Control server, you can download the installation files for the target, controller, and cli components. The controller installation file is for the standard controller. For the FIPS-compliant controller installation file, use the additional setup utility.


1. Click **Tools > Downloads**.
2. Select **Agent Downloads**.
3. Select the relevant component file.

Install the server

BigFix Remote Control server supports the following installation types:

Table 8. Server installation types

Automated installation - For more information, see Installing by using the server installer (on page 32)	Manual Installation - For more information, see Installing on WebSphere Application Server version 8.5: deploying the war file (on page 44)
Available on Windows® operating system and Linux operating system.	Available on AIX operating system and Solaris operating system and for any operating system that WebSphere Application Server 8.5 supports.
Derby is installed as embedded or uses existing supported database. Local or remote.	Database must be created or an existing supported database can be used.
All embedded components are installed locally on the same computer.	The database can be installed on a separate computer.

 **Note:** The embedded Derby database is not supported in production.

Set up the database

Before you set up the database, install the database software and create the instance where the database for BigFix Remote Control is held.

Setting up DB2

To perform the database setup for DB2 complete the following steps. If you are using a Windows operating system, begin from step [2 \(on page 26\)](#). If you are using Linux operating system or AIX operating systems, begin from step [1 \(on page 26\)](#):

1. To verify that DB2 and the instance are ready for remote connectivity using TCP/IP complete the following steps:

- a. Run `db2 get database manager configuration` and verify that the value of **svcname** is a valid port.

```
for example 50000

or a reference mapped to a valid port

for example, db2c_db2inst1.
```

- b. Ensure that the configured port is not used by other processes in the system, or blocked by a firewall that sits between the Application Server host and the DB2 server.

- c. Use the `db2stop` command to stop the DB2 instance.

Set **DB2COMM** to `tcPIP` with the command

```
db2set DB2COMM=tcPIP
```

Run `db2start` to start the DB2 instance again.

The DB2 server is now ready for accessing over the network.

2. Create the database that BigFix Remote Control will use by running the following command as the instance owner:

 **Note:** Not necessary when the database is local.

```
db2 create db databasename using codeset UTF-8 territory requiredterritory
```

where *databasename* is the name required for the database. This database name must be the name that was referenced in any configuration settings. For example, TRCDB.

requiredterritory is the required territory. For example, GB for Great Britain.

3. Verify the privileges that a specific user, for the database, needs to have.

Do not use the **db2inst1** user as the user configured to access the BigFix Remote Control database. Create a new specific user for DB2 that has the database owner privileges.

With the blank database created and ready to use, the next step is to set up the WebSphere server, see [Setting up the application server \(on page 44\)](#). It is possible to verify that the database is set up properly by using a DB2 client to connect to the database from another host. For more details see the DB2 Infocenter.

Setting up Oracle

To set up Oracle to use with BigFix Remote Control, create the database and then set up the database permissions.

Creating the database

Run the Oracle database configuration assistant to create the database.

To create the Oracle database that will be used for BigFix Remote Control, complete the following steps:

1. Run the Oracle database configuration assistant.

Windows systems


For example, Select **Start > All Programs > Oracle > Configuration and Migration Tools > Database Configuration Assistant**.

UNIX®-based systems

Enter the command dbca from the `$ORACLE_HOME/bin` directory.

2. Click **Next** on the welcome screen.
3. **Step 1:** Select **Create a Database**. Click **Next**.
4. **Step 2:** Select **General Purpose** for the template. Click **Next**.
5. **Step 3:**
 - a. Specify a name for the database. For example, TRCDB.
 - b. Specify an SID to be used to reference the database. For example, TRCDB.Click **Next**.
6. **Step 4:** Select the database management option that you require. For example, **Use Database Control for Database Management**. Click **Next**.
7. **Step 5:** Specify a password for the database and confirm the password. For example, dboracle. Click **Next**.

8. **Step 6:** Specify where the database will be stored. For example, `File System`. Click **Next**.
9. **Step 7:** Specify locations for the database files. For example, `Use Database File Locations from Template`. Click **Next**.
10. **Step 8:** Select the recovery options for the database. Click **Next**.
11. **Step 9:** On the Database Content window, click **Next**.
12. **Step 10:** On the Initialization Parameters screen select the **Character Sets** tab.
 - a. Select the required Database Character Set
 - b. Click **Next**.
13. When you are using Oracle 11g, the following two steps are also required.
 - a. Security Settings, accept the enhanced 11g default security settings.
 - b. Automatic Maintenance Tasks, enable automatic maintenance tasks.
14. **Step 11:** On the Database Storage window click **Next**.
15. **Step 12:** Select the required Creation Options. Click **Finish**.
16. On the Confirmation screen, click **OK** to start the database creation.

 **Note:** This may take some time as it goes through the different stages.
17. Click **Exit** when the database creation is complete.

The Oracle database that will be used for BigFix Remote Control is created.

Setting up database permissions

When you have created the Oracle database that will be used for BigFix Remote Control you will need to configure its permissions.

To configure the database permissions complete the following steps:

1. Run Oracle SQL*Plus.

Windows systems

For example: Click **Start > Programs > Oracle-OraHomeName > Application Development > SQL Plus**.

Alternatively, enter the following command at a command prompt.

sqlplusw

Log on using the database user name and password and click **OK**. See your database system administrator if you do not have this.

For example:

Username - system

Password - dboracle

Linux systems

Open a UNIX or a Windows terminal and enter the SQL*Plus command:

```
sqlplus username / password @connect_identifier
```

username and *password* are the database credentials required to connect to the database.

connect_identifier is the connection required for your specific database.

For example, @TRCDB as SYSDBA

```
@//servername:port/DatabaseSID as SYSDBA
```

servername is the server name or IP address of the system where your Oracle installation is located.

port is the port of the system where your Oracle installation is located.

DatabaseSID is the SID defined for the database you created.

The SQL*Plus executable is installed in `$ORACLE_HOME/bin`, which is included in your operating system PATH environment variable. You may need to change directory to the `$ORACLE_HOME/bin` directory to start SQL*Plus.

2.

After SQL*Plus has started and connected to the database you can create the required users and grant permissions. There are two methods for creating users and granting permissions. Choose the appropriate method for creating the users.

Create one user ID in Oracle which will also be used to log on to BigFix Remote Control.

Create a single user. The user must be called Asset. This user ID is used by BigFix Remote Control to create and log on to the database, and use the database.


Issue the following commands to create the user ASSET.

a. connect SYS/PASSWORD@DATABASE AS SYSDBA;

where *PASSWORD* is the default Oracle user password.

and *DATABASE* is the database name that was defined when creating the database. For example, TRCBD.

- b. CREATE USER ASSET IDENTIFIED BY PASSWORD DEFAULT TABLESPACE users
TEMPORARY TABLESPACE temp;

 **Note:** PASSWORD can be changed to whatever you require, for the user ASSET.

- c. GRANT UNLIMITED TABLESPACE TO ASSET;
- d. GRANT CONNECT TO ASSET;
- e. GRANT CREATE INDEXTYPE TO ASSET;
- f. GRANT CREATE SEQUENCE TO ASSET;
- g. GRANT CREATE TABLE TO ASSET;
- h. GRANT CREATE TRIGGER TO ASSET;
- i. GRANT CREATE INDEXTYPE TO ASSET;
- j. GRANT CREATE PROCEDURE TO ASSET;
- k. GRANT CREATE VIEW TO ASSET;
- l. GRANT ANALYZE ANY TO ASSET;

Create a separate user ID to log on to BigFix Remote Control

Create 2 users. User 1 must be called Asset. This user has no specific permissions and is used only as a schema name. User 2 is the main user and can be called anything you require. This user is used by BigFix Remote Control to create and logon to the database, and use the database. Use the assistant tool to create user TRCDBU.

Complete the following steps to create the required permissions for user TRCDBU.

- a. GRANT UNLIMITED TABLESPACE TO ASSET;
- b. GRANT UNLIMITED TABLESPACE TO TRCDBU;
- c. GRANT ALTER ANY INDEX TO TRCDBU ;
- d. GRANT ALTER ANY INDEXTYPE TO TRCDBU ;
- e. GRANT ALTER ANY PROCEDURE TO TRCDBU ;
- f. GRANT ALTER ANY SEQUENCE TO TRCDBU ;
- g. GRANT ALTER ANY TABLE TO TRCDBU ;
- h. GRANT ALTER ANY TRIGGER TO TRCDBU ;
- i. GRANT COMMENT ANY TABLE TO TRCDBU ;
- j. GRANT CREATE ANY INDEX TO TRCDBU ;
- k. GRANT CREATE ANY INDEXTYPE TO TRCDBU ;
- l. GRANT CREATE ANY SEQUENCE TO TRCDBU ;
- m. GRANT CREATE ANY TABLE TO TRCDBU ;

- n. GRANT CREATE ANY TRIGGER TO TRCDBU ;
- o. GRANT CREATE INDEXTYPE TO TRCDBU ;
- p. GRANT CREATE PROCEDURE TO TRCDBU ;
- q. GRANT CREATE SEQUENCE TO TRCDBU ;
- r. GRANT CREATE TABLE TO TRCDBU ;
- s. GRANT CREATE TRIGGER TO TRCDBU ;
- t. GRANT CREATE VIEW TO TRCDBU ;
- u. GRANT DELETE ANY TABLE TO TRCDBU ;
- v. GRANT INSERT ANY TABLE TO TRCDBU ;
- w. GRANT DROP ANY INDEX TO TRCDBU ;
- x. GRANT DROP ANY INDEXTYPE TO TRCDBU ;
- y. GRANT DROP ANY PROCEDURE TO TRCDBU ;
- z. GRANT DROP ANY SEQUENCE TO TRCDBU ;
- aa. GRANT DROP ANY TABLE TO TRCDBU ;
- ab. GRANT DROP ANY TRIGGER TO TRCDBU ;
- ac. GRANT EXECUTE ANY INDEXTYPE TO TRCDBU ;
- ad. GRANT EXECUTE ANY LIBRARY TO TRCDBU ;
- ae. GRANT EXECUTE ANY TYPE TO TRCDBU ;
- af. GRANT SELECT ANY SEQUENCE TO TRCDBU ;
- ag. GRANT SELECT ANY TABLE TO TRCDBU ;
- ah. GRANT UNLIMITED TABLESPACE TO TRCDBU ;
- ai. GRANT UPDATE ANY TABLE TO TRCDBU ;
- aj. GRANT ANALYZE ANY TO TRCDBU ;

Setting up MSSQL

To set up MS SQL to use with BigFix Remote Control, create the database and then set up the database permissions.

Creating the database

Use the MS SQL management studio to complete the following steps:

 **Note:** During the installation of MS SQL, mixed mode authentication should have been set up.

1. Click **Connect**.
2. Right-click the **server tree** and click **properties**.
3. Select **security**.

4. Ensure that SQL server and authentication mode is selected.
5. Expand the **server tree**.
6. Right-click **databases**.
7. Select **Create New Database**.
8. Enter a name for the database. For example, TRCDB. Click **OK**.

The default owner of the database is user sa, the system administrator. Create a new user, to be the owner of the database being used with BigFix Remote Control.

Database permissions

The default system administrator is the owner of the database and therefore has the required permissions for using the database. If you have created a new user, they also have the required permissions if they have been assigned as the owner of the database.

Installing by using the server installer

The BigFix Remote Control server installer can be used on Windows operating systems, Red Hat Linux operating systems, and SUSE Linux operating systems. A fully functional self-contained server with either of the following component setup is installed.

- BigFix Remote Control server with WebSphere Application Server Liberty Profile version 16.0.0.2 and a Derby version database.
- BigFix Remote Control server with WebSphere Application Server Liberty Profile version 16.0.0.2 and one of the following databases:
 - IBM DB2 10.x, 11.x Workgroup(WSE) and Enterprise Edition(ESE).
 - Oracle 11g and 12c.


When you use an Oracle database, if you are using the Oracle 11g drivers, set `oracle.increment.keys.off=1` in the `trc.properties` file. Restart the server service.

- Microsoft SQL server 2008, 2012, 2014, and 2016.

You must use a JDBC driver whose version is bigger than 6.3. Older versions do not support TLS1.2 or JRE8.

When you use an MS SQL database, Windows authentication is not supported. You cannot log on with a domain user. You must use mixed mode authentication and create an SQL user to connect to the database.


For more information about the supported versions of the installed components, see [Server requirements \(on page 9\)](#)

 **Note:** Click **Cancel** at any time to end the installation.

Approximate installation time

- Specifying options in the installer: 5 - 10 minutes.
- Installation of the software: 5 minutes.

1. A minimum screen resolution of 1024 by 768 pixels is recommended when you are using the installer.
2. On a Linux operating system, you must install **libstdc++.so.5** when you are installing and configuring the operating system. If this package is not installed, you can install package **compat-libstdc++-33**, which contains **libstdc++.so.5**.

 **Note:** During the file copy phase of the server installation, a backup copy of any existing installation is saved. This feature is useful if a problem occurs with the installation when you are upgrading. The following directory is deleted if it exists.

`[INSTALLDIR]/trcserver.bak.`

The current server installation in `[INSTALLDIR]/wlp/usr/servers/trcserver` is then renamed or moved to `[INSTALLDIR]/trcserver.bak`.

You can access the backup directory to restore or recover anything from the previous installation.

To install the BigFix Remote Control server application, complete the following steps:

1. Run the server installation file relevant to your operating system.

Windows systems


`trc_server_setup.exe`

Linux systems

`trc_server_setup.bin`


To obtain the installation file see [Obtain the installation files \(on page 22\)](#).

2. Choose the language and click **OK**.
3. At the **Introduction** window click **Next**.
4. Click to accept both the IBM and non-IBM terms, click **Next**.
5. Accept the default location or click **Choose** to define a location for the installation files, click **Next**.

 **Note:** WebSphere Application Server cannot be installed in a directory with a name that contains non-English-language characters. This installation installs an embedded version of WebSphere

Application Server. Therefore, you must choose a destination for the installation files that do not contain any non-English-language characters.


6. Select the database, click **Next**.

 **Note:** Derby is embedded in the application and is installed locally when you select Derby. To use DB2 or Oracle, you must install them and create a database instance before you install BigFix Remote Control.

7. Enter the options for your selected database and click **Next**.

Derby


- a. Specify a name for the database, click **Next**. For example, `TRCDB`.

 **Note:** If you are using an existing database, you can choose to drop the database.

DB2

Database server

The IP address or host name of your database server.

 **Note:** 127.0.0.1 can be used when DB2 is installed locally. If you install DB2 on a remote system, type the IP address of the remote system.

Port

Port on which DB2 is installed.

 **Note:**

- a. On Windows® systems, the default port is 50000. On Linux systems, the default port is 50001.
- b. A remote DB2 installation is limited to type four connections. A local installation can use type two or four. For type two connections, set the port value to 0.

Administrator Userid

Specify the Administrator user ID that is used for logging on to the database. The user ID must have admin access to the database.


If you select **create database**, the user ID must have administrator access for DB2.

Administrator password

Specify the Administrator password for connecting to the database.


Database Name

Specify a name for the database. For example, `TRCDB`.

 **Note:** If you are using a remote database, type the name of the database that was created on the remote system.


Directory path to db2jcc.jar file

Specify the path to the DB2 JAR files, `db2jcc.jar`, and `db2jcc_license.jar`

 **Note:** If you are using a remote database share the drive, on the remote system, that the DB2 JAR files are in. Enter the shared drive location.

Create database

If DB2 is installed locally (127.0.0.1), you can select to create a blank database during the installation. You can also select to drop an existing local database and create a new database.

 **Note:** Do not select create database or drop database if you are using a remote database.

Path for database install

Specify the path where the database can be installed. If the installation is local and you select to create the database, the admin user who is specified must have the appropriate authority. On a Windows system, use the `db2admin` user, and on a Linux system, the user must be a member of the group `db2grp1`.

 **Note:**

Linux systems

Specify a directory that the admin User ID has read and write permissions for.

Windows systems

Specify a drive letter.

Oracle

Database server


The IP address or host name of your database server. 127.0.0.1 can be used when Oracle is installed locally. If you install Oracle on a remote system, type in the IP address of the remote system.

Port

Port on which Oracle is installed.

Administrator Userid

Specify the administrator user ID that is used for logging on to the database. The user ID must have admin access to the database.

 **Note:** For an Oracle installation, a user that is called **asset** must exist. This user ID can be used here or use an existing or new user.

Administrator password

Specify the administrator password for connecting to the database.

Database Name

Specify a name for the database. The name is the SID name on the server, not the one in `tnsnames.ora`. For example, `TRCDB`.


Directory path to the oracle Java JDBC library

Specify the path to the oracle Java JDBC library. The location can be obtained from the Oracle server installation or downloaded from the Oracle website. For example, `c:\oracle\ora92\jdbc\lib\ojdbc14.jar`

MSSQL

Database server

The IP address or host name of your database server.

 **Note:** 127.0.0.1 can be used when MS SQL is installed locally on a Windows system only.

Port

Port on which MS SQL is installed.

Administrator Userid

Specify the administrator user ID that is used for logging on to the database. The user ID requires admin access to the database.

Administrator password

Specify the administrator password for connecting to the database.

Database Name

Specify a name for the database. For example, `TRCDB`.

Directory path to the MS JDBC Java files

Specify the path to the MS JDBC Java files. The `mssql-jdbc-X.X.X.jre8.jar` file must be used depending on the version of MS SQL database that you are using.

If installed on the same server, select to create database

If MS SQL is installed locally, you can select to create the database.

Drop the database if installed locally

Select if you already have an existing database with the name that is entered for **Database Name** that you do not want to use.

If local, select path where to create the database

Specify the database installation path. If the installation is local and you select to create the database the Admin user must have appropriate authority to do so.

Linux systems.

Specify a directory that the admin User ID has read and write permissions for.

Windows systems.


Specify an existing directory.

8. Specify the web server parameters then click **Next**.


Force targets to use HTTPS

Select this option for the target software to communicate with the server by using the HTTPS URL. The **enforce.secure.endpoint.callhome** and **enforce.secure.endpoint.upload** properties in the `trc.properties` file are also set to *true*. The check box is selected by default on a new installation.

Regardless of your selection, the **enforce.secure.web.access**, **enforce.secure.weblogon**, and **enforce.secure.allogon** properties that enable HTTPS logon and access to the web portal, are all set to *True* by default. For more information about these properties, see Set a secure environment the *BigFix Remote Control Administrator's Guide*.

 **Note:** If you are using HTTPS, you must use a fully qualified domain name for the server name.

Select whether the server and target software communicates by using HTTP or HTTPS. The check box is selected by default. Regardless of your selection, the **enforce.secure.web.access**, **enforce.secure.endpoint.callhome**, **enforce.secure.endpoint.upload**, **enforce.secure.weblogon**, and **enforce.secure.allogon** properties that enable HTTPS logon and access to the web portal, are all set to *True* by default. For more information about how to configure a secure environment, see the *BigFix Remote Control Administrator's Guide*.


 **Note:** If you are using HTTPS, you must use a fully qualified domain name for the server name.

Use secure registration tokens to register targets

Select this option to enable the secure target registration feature. This feature prevents unauthorized targets from registering with the BigFix Remote Control server. The check box is selected by default on a new installation. Ensure that the **Force targets to use HTTPS** option is also selected. For more information about secure registration, see [Enable secure target registration \(on page 114\)](#).

Upload data to server

The fully qualified name for the BigFix Remote Control server. For example,
`trcserver.example.com`

 **Note:** You must make sure that you enter the fully qualified name. The name is used for creating the URL in the `trc.properties` file that is passed to the target after it contacts the server for the first time. If the fully qualified name is incorrect, the target might not be able to contact the server successfully when it is next due to contact it.

Web path of URL

Specify the web path for the server URL. For example, `/trc`.

Server port on Webserver (default 80)


Specify a port for the server.

SSL Port (default 443)

Specify a port for SSL.

Administrator email

Specify an administrator email address. For example, `admin@company.com`.

 **Note:** To use the email function, you must install a mail server. Edit the `trc.properties` file after you install the BigFix Remote Control server. For more information about editing the properties files, see the *BigFix Remote Control Administrator's Guide*

Advanced port configuration

Select this option to change port values when you click Next. If any of the port values that are displayed are being used by other applications, change the value to avoid conflict.

Enable FIPS

Select this option to enable FIPS compliance on the server. For more information about enabling FIPS compliance, see [Federal information processing standard \(FIPS 140-2\) compliance in BigFix Remote Control \(on page 150\)](#).


Enable NIST SP800-131A Compliance (Enables FIPS)

Select this option to enable NIST SP800-131A compliance on the server. For more information about enabling NIST SP800-131A compliance, see [NIST SP800-131A compliance in BigFix Remote Control \(on page 163\)](#).

9. Select the secure web settings parameters and click **Next**.

click for HTTPS / unclicked for HTTP

Select whether the server and target software communicates by using HTTP or HTTPS. Use HTTPS is the default value.

 **Note:** If you are using HTTPS, you must use a fully qualified domain name for the server name.

Enforce secure web access

An HTTP request that is not a call home, upload, or validation request is redirected to the secure URL. The value that is set in the `secure.url` property is used as a base.

Selected

The HTTP request is redirected to the secure URL. This value is the default value.

Not selected

The HTTP request is not redirected to the secure URL.

Enforce secure callhome


Determines the URL that a target uses to contact the BigFix Remote Control server.

Selected

If a call home is received by using HTTP, the request is redirected to the secure URL. The secure URL is also returned in the response from the server. Targets are forced to use the secure URL when they send heartbeats to the BigFix Remote Control server. This value is the default value.

Not selected

Targets are not forced to use the secure URL when they send heartbeats to the BigFix Remote Control server. This value is the default value.

 **Note:** From BigFix Remote Control V9.1.3, HTTPS secure communication is enforced by setting the **url** property in the `trc.properties` file to HTTPS when **Force targets to use https** is selected during installation. To ensure HTTP target communication, confirm that the **url** property is set to the HTTP URL in the `trc.properties` file. If the **url** property is set to HTTPS, the targets use HTTPS after they first contact the server.

Enforce secure upload


Determines the URL that a target uses to contact the BigFix Remote Control server.

Selected

If an upload or a validation request is received by using HTTP, the server redirects the request to an equivalent URL. The equivalent URL is built with the value that is defined in **secure.url** as a base. It also uses the value of **secure.url** as a base to provide the upload and validation URLs to the controller and target when the session starts. This value is the default value.

Not selected

The server does not redirect to the secure URL if an upload or a validation request is received by using HTTP.

 **Note:** From BigFix Remote Control V9.1.3, HTTPS secure communication is enforced by setting the **url** property in the `trc.properties` file to HTTPS when **Force targets to use https** is selected during installation. To ensure HTTP target communication, confirm that the **url** property is set to the HTTP URL in the `trc.properties` file. If the **url** property is set to HTTPS, the targets use HTTPS after they first contact the server.

Enforce secure web logon

Make the default log on action from the web UI use HTTPS. This property requires **secure.url** to be set with the full host name.

Selected

Logons from the BigFix Remote Control Server UI use HTTPS. Logons that use HTTP through another tool or page are not prevented.

HTTPS is not shown in the URL, but the logon page with USERID/PASSWORD is posted as HTTPS. The **secure.url** parameter is used. If this property is set incorrectly, the logon does not succeed. This value is the default value.

Not selected

Log on by using HTTP or HTTPS, whichever is entered in the browser URL.

Enforce secure all logon

Force any logon action to use HTTPS, deny any logon that does not use HTTPS. This property requires **secure.url** to be set with the full host name.

Selected

Any logon attempt that uses HTTP is rejected and redirected to the logon page. This value is the default value.


Not selected

Log on by using HTTP or HTTPS, whichever is entered in the browser URL.

10. Select options for your SSL certificate and click **Next**. The certificate configuration is stored in the `ssl.xml` file.

Use an auto generated certificate store

Select this option to use a self-signed certificate that is generated by the installer.

 **Note:** If the following options are not enabled, click **Use an auto generated certificate store** to enable them.

Overwrite an existing certificate store.

If a self-signed certificate store is already saved, the new certificate overwrites the saved certificate store. This option is the default option.

Password for a new or a previously generated certificate store.

Type a new password for the self-signed certificate. If you do not select to overwrite, type the password for your existing auto generated certificate store. If left blank, the default password **TrCWebAS** is saved as the password. The password must have a minimum of 6 characters.

Select an existing certificate store

Select this option to use an existing certificate store that is already saved.

Select existing certificate store location.

Click **Choose** to browse to the relevant certificate store. Select the certificate store. The file extension can be `.jks` or `.p12`.

When you use an existing certificate store, it is not copied to the installation directory during installation. The server software instance points to the location of the certificate store that you provide. Therefore, you must make sure that you save the certificate store to an adequate location on the server before you start the server installation. The certificate store must be stored in a location that does not get deleted. Therefore, do not save the file in the `[installdir]\wlp` directory or any of its subdirectories. Do not delete the certificate store at the end of the installation.

If you select a previously saved auto-generated certificate store from the server installation directory, a warning is displayed. Choose **Copy file** to copy the file to a location that is not deleted during the installation. If the file is not copied successfully, you must manually copy the certificate

store file to another location. Click **Choose** and select the new location of the file.

Click **Restore Default** to reset the field value to its original value.

Enter the certificate store password.

Type a password for the certificate store.

11. Select options to configure Single-Sign-On (SSO) and click **Next**. The SSO configuration is stored in the `sso.xml` file.

Enable SSO

Select this option to enable Single-Sign-On (SSO). To continue with the configuration, you must get the SAML metadata XML file from the Identity Provider (IdP) and which hash algorithm they are using: SHA-1 or SHA-256. After the server starts, download the SP metadata and provide it to the IdP to establish federation between this SP and the IdP. Type the following URL in your browser to download the metadata: `HTTPS://[rc-server-url]:443/ibm/saml20/defaultSP/samlmetadata`, where `[rc-server-url]` is the URL of your remote control server. You must also add users to the remote control database so that they can log on by using SSO.

Metadata XML file

Click **Choose** and select the SAML metadata XML file that you obtained from the IdP.

Algorithm used to sign SAML messages

Select the signature algorithm (SHA-1 or SHA-256) to use to sign messages in communications between the Identity Provider (IdP) and this Service Provider (SP) which is the BigFix Remote Control Server.

Advanced parameters (optional)

Type in further configuration options, by adding attribute names in a space-separated list, in the following format: `[keyword]=[keyword-value]`. Where `[keyword]` is the attribute name and `[keyword-value]` is the attribute value. For more information about further configuration parameters, see [SAML Web SSO 2.0 Authentication \(samlWebSso20\)](#).


Force regeneration of SAML data. (you must re-register with the IdP)

The first time that you enable SSO, a new default SAML certificate keystore is created. For future upgrades, you can select the regeneration option to create a new default certificate keystore. The current keystore is deleted and the new one is saved. When

you select this option, you must reestablish the connection between the SP and the IdP after the server restarts.

12. Select a location for the product icons to be displayed.

If you select Other, click **Choose** to specify a location.

 **Note:** Product icons do not work when you are using Linux.

13. In the **Summary** pane, click **Install**.

14. If you selected to enable SSO, a pane that is labeled as **Important** is displayed. Take note of the URL and information and click **Next**.

15. Click **DONE** to complete the installation.

The BigFix Remote Control server software is installed including a set of properties files. These files can be edited to configure your environment.

 **Note:**

1. It is important to make sure that the **URL** property in the `trc.properties` file contains the correct URL for the BigFix Remote Control server. This property is used when targets contact the server and for determining the server during a remote target installation. If the URL property value is not correct, the remote targets are not able to contact the server successfully. Therefore, you might have problems when you start remote control sessions with the targets.
2. If the IP address of the server changes at any time, make sure that you update the URL property in `trc.properties`. Restart the server service because the targets try to contact to the old IP address until the change to the property is made.

Installing on WebSphere Application Server version 8.5: deploying the war file


BigFix Remote Control includes a license for WebSphere Application Server v8.5.

This license can be used for installations on AIX systems since the option of using the embedded Liberty profile is not available for these systems. However, this option is also available to customers that prefer to use the WebSphere Application Server on Windows systems or Linux systems.

As described in the prerequisites section, a database needs to be created for BigFix Remote Control. After the database is created, add it to the WebSphere data sources.

Setting up the application server

A regular installation of WebSphere 8.5 Base must be installed. Installation of the server war file requires the use of a Java 7 environment in the Application Server. For more information about the Java requirements, see <http://www-01.ibm.com/support/docview.wss?uid=swg21976905>

 **Note:** It is necessary to create the WebSphere profile in a folder that does not include any spaces in its path. Otherwise, unrecoverable issues might occur when you deploy the application war file.

Use the **WebSphere Integrated Solution Console** to configure the application server.

To access the Integrated Solution Console, complete the following steps:

1. In your browser type

```
https://[server : port]/ibm/console  
  
where server is the IPaddress or name for the application server machine  
  
for example localhost or 192.0.2.0  
  
and port is the port that the server is listening on.
```

The default port for the WebSphere Application Server admin console is 9060.

2. Log on with the ID and password that you defined when you installed WebSphere.

DB2 configuration

Creating DB2 database authentication data

Creating authentication data for connecting to an BigFix Remote Control DB2 database

Credentials to use for the database connection need to be established and added as a new entry to the JAAS-J2C authentication data.

To create an entry complete the following steps:

1. Click **Security > Global Security**.
2. On the right of the screen, expand **Java Authentication and Authorization Services** .
3. Click **J2C authentication data**.
4. Click **New** to add a new entry.

5. Supply the following information:

Alias

Specify a name for the authentication alias.

Userid

Type the user ID that was defined when DB2 was installed. Can be one of the following users.

- The user who has permissions to access the TRCDB database, if a specific user was created.
- The DB2 owner instance, **db2admin** in a Windows system and **db2inst1** in UNIX / Linux system.

Password

Type the password that you defined when you installed DB2.

6. Click **OK**.

7. Click **Save**.

Verifying the Websphere variables

The JDBC Provider uses WebSphere environment variables to define the paths to the JDBC driver JAR files.

- db2jcc.jar
- db2jcc-javax.jar
- db2jcc-license_cu.jar
- db2jcc4.jar. If available.

Verify that the correct values are defined by completing the following steps:

1. Select **Environment / WebSphere Variables**.
2. Click **DB2UNIVERSAL_JDBC_DRIVER_PATH** and verify that this points to the DB2 libraries.

Local DB2 database

If you have installed the DB2 database locally the files are located in

Windows systems

`\Program Files\ibm\sqlllib\java`

Linux systems

```
/opt/ibm/db2/VERSION/java
where VERSION is the DB2 version number
for example: /opt/ibm/db2/V8.1/java
```

Remote DB2 database

If you are using a remote DB2 database you must copy the jar files from the remote system to a location on your local system and put the path to the local files here.

3. Click **OK**.
4. Click **Save**.

Creating the DB2 data source

When you have verified that the JDBC Provider is configured properly, the data source for BigFix Remote Control must be created using that JDBC Provider.

To create the data source complete the following steps:

1. Select **Resources > JDBC > Data Sources**.
2. Select the scope from the drop down menu that includes the node and the server.
For example, Node=TEST-2008Node02, Server=server1.
3. Click **New**.
4. Specify the data source information.


- a. Enter basic data source information

Data source name

Specify a name for the data source. This can be any required name.

JNDI Name

This should be set to `jdbc/trcdb`

 **Note:** If this name is changed, you need to change the **common.properties** file also.

- b. Select JDBC Provider

The data source will use the Universal JDBC Provider for DB2 that is predefined in WebSphere.

- i. If **DB2 Universal JDBC Driver Provider** is available, select **Select an existing JDBC provider** from the list. If it is not available, click **Create new JDBC provider**.
 - ii. In the Database type list, select **DB2**.
 - iii. Select **DB2 universal JDBC Driver provider**.
 - iv. From the **Implementation type** list, select **Connection pool data source**.
 - v. Click **Next**.
 - vi. Accept the default values and click **Next**.
- c. Enter database specific properties for the data source
- Driver Type**
- Select 4 from the list.
- Database name**
- This is the name used when the **db2 create db** command was issued.
- Server name**
- This is set to the IP or host name of the server where DB2 is installed. If DB2 is installed locally you can use localhost.
- Port number**
- This is set to the port that was configured in DB2 for remote connections.
- Click **Next**.
- d. Setup security aliases
- i. From the **Component-managed authentication alias** list, select *your node*/DB2 where *your node* is the node you previously created for DB2.
 - ii. Accept the default of **none** in the remaining lists.
 - iii. Click **Next**.
- e. Review the summary and click **Finish**.
5. To save the configuration changes, click **Save**.

When the data source has been created and the changes to the profile are saved, test that the data source is correctly configured. Select the data source from the list of data sources and click Test connection. If the connection is successful, a conformation message is displayed. A failure in the test should be corrected before continuing with the installation, as BigFix Remote Control will not work without a valid data source.

Oracle configuration

Creating Oracle database authentication data

Credentials to use for the database connection need to be established and added as a new entry to the JAAS-J2C authentication data.

To create an entry complete the following steps:

1. Click **Security > Global Security**.
2. On the right of the screen, expand **Java Authentication and Authorization Services** .
3. Click **J2C authentication data**.
4. To add a new entry, click **New** .
5. Supply the following information:

Alias

Specify a name for the authentication alias.

Userid

Type the ID that was defined when the Oracle database was created. This is the user that you created permissions for.

Password

Type the password that was defined when Oracle was installed.

6. Click **OK**.
7. Click **Save**.

Creating the Oracle JDBC provider

To establish access to your Oracle database you must create a JDBC provider for Oracle access.

To create the JDBC provider complete the following steps:

1. Select **Resources > JDBC > JDBC Provider**.

2. Select Scope and choose the one which has Node and Server.

3. Click **New**.

4. Specify the JDBC provider information

Database type

Set to Oracle.

Provider Type

Set to Oracle JDBC Driver.

Implementation type

Set to Connection Pool datasource.

5. Click **Next**.

6. The Class path is already pre-populated as `${ORACLE_JDBC_DRIVER_PATH}/ojdbc6.jar`. The directory location for `${ORACLE_JDBC_DRIVER_PATH}` to the jar files must be correct. This can be obtained from the Oracle server installation or downloaded from the Oracle website. For example, `C:\app\Administrator\product\11.2.0\dbhome_1\jdbc\lib`. Click **Next**.

7. Click **Finish**.

8. Click **Save**.

Verifying the Websphere variables

The JDBC Provider uses WebSphere environment variables to define the paths to the JDBC driver JAR files. Verify that the correct values are defined by completing the following steps:

1. Select **Environment / WebSphere Variables**.

2. Click **ORACLE_JDBC_DRIVER_PATH**

and verify that this points to the directory location chosen in step [6 \(on page 50\)](#) in the Creating the Oracle JDBC Provider section.

3. Click **OK**.

4. Click **Save**.

Creating the Oracle data source

When you have verified that the JDBC Provider is configured properly, the data source for BigFix Remote Control must be created using that JDBC Provider.

To create the data source complete the following steps:

1. Select **Resources > JDBC > Data Sources**.
2. Select the scope with Node and Server.
3. Click **New**.
4. Specify the data source information


- a. Specify the data source information.

Data source name

Specify a name for the data source. This can be any required name.

JNDI Name

This should be set to `jdbc/trcdb`

 **Note:** If this name is changed, further changes to the **common.properties** file are also required.

Click **Next**.

- b. Select JDBC provider

Click **Select Existing JDBC provider** and select **Oracle JDBC Driver**. Click Next.

- c. Enter database specific properties for the data source.

URL

`url=jdbc:oracle:thin@dbserver:1521:SID`

where *dbserver* is the IP address of the server.

SID is the Oracle database SID.

Data store helper class name

Accept the default Data store helper class name, **Oracle 11g.data store helper**.

Accept remaining default selected values and click **Next**.

- d. Set up security aliases

- i. Select **Component-managed authentication alias** and select the alias you previously created for Oracle.
 - ii. Accept the default of **none** in the remaining lists.
 - iii. Click **Next**.
 - e. On the summary screen, click **Finish** to create the data source.
5. Click **Save**.

You can select the newly created datasource and click **Test**, to test connectivity.

MS SQL configuration

Creating authentication data

Credentials to use for the database connection need to be established and added as a new entry to the JAAS-J2C authentication data.

To create an entry complete the following steps:

1. Click **Security > Global Security**.
2. On the right, expand **Java Authentication and Authorization Services**.
3. Click **J2C authentication data**.
4. To add a new entry, click **New**.
5. Supply the following information:

Alias

Specify a name for the authentication alias.

Userid

Type the ID that was defined when MS SQL was installed. This is the user that you created permissions for. Default is **sa**.

Password

Type the password that was defined when MS SQL was installed.

6. Click **OK**.

7. Click **Save**.

Creating the JDBC provider

To establish access to your MS SQL database you must create a JDBC provider for MS SQL access.

To create the JDBC provider complete the following steps:

1. Select **Resources > JDBC > JDBC Provider**.
2. Select **Scope** and choose the one which has Node and Server.
3. Click **New**.
4. Specify the JDBC provider information.

Database type

Set to `SQL Server`.

Provider Type

Set to `Microsoft JDBC Driver`.

5. Select Connection pool data source.
6. Click **Next**.
7. To accept the path to the jar files, click **Next**.
8. Click **Finish**.
9. Click **Save**.

Verifying the Websphere variables


The JDBC Provider uses WebSphere environment variables to define the paths to the JDBC driver JAR files. The correct jdbc driver software must be downloaded from Microsoft. The following version is recommended:

Microsoft JDBC Driver 4.0 for SQL Server - `sqljdbc_4.0.2206.100_enu.exe`

Download the SQL Server jdbc driver and copy it to the root drive of the server. Run the file to extract the driver. The `sqljdbc4.jar` file is extracted to the following directory structure:

`C:\extract_path\sqljdbc_4.0\enu\`

where *extract_path* is the directory chosen when you unzipped the file.

 **Note:** The path cannot contain any spaces.

Verify that the correct values are defined by completing the following steps:

1. Select **Environment / WebSphere Variables**.
2. Click **MICROSOFT_JDBC_DRIVER_PATH** and verify that this points to the Microsoft SQL Server JDBC driver, sqljdbc4.jar file that you extracted.
3. Click **OK**.
4. Click **Save**.

Creating the MS SQL data source

When you have verified that the JDBC Provider is configured properly, the data source for BigFix Remote Control should be created using that JDBC Provider.

To create the data source complete the following steps:

1. Select **Resources > JDBC > Data Sources**.
2. Select the scope with Node and Server.
3. Click **New**.
4. Specify the data source information


- a. Enter basic data source information

Data source name

Specify a name for the data source. This can be any required name.

JNDI Name

This should be set to **jdbc/trcdb**

 **Note:** If this name is changed, the **datasource.context** property in the `common.properties` must be changed after the WAR file is deployed. After the correct value is set, save the file and restart the application from the Websphere admin console.

- b. Select JDBC provider

Select **Microsoft SQL Server JDBC Driver** or the required JDBC provider. Click **Next**.

- c. Enter database specific properties for the data source

Database name

This is the name used when you created the MS SQL database.

Port number

Port used when installing MS SQL. Default is 1433.

Server name

This is set to the IP or hostname of the server containing the MS SQL installation. If MS SQL is installed locally you can use localhost.

- d. Set up security Alias

- i. Select **Component-managed authentication alias** and select the alias you previously created for MS SQL.
- ii. Accept the default of **none** in the remaining lists.
- iii. Click **Next**.

- e. On the summary screen, click **Finish** to create the data source.

5. Click **Save**.

Deploying the BigFix Remote Control application

After you install and set up the application server, deploy the application code for BigFix Remote Control on the WebSphere server. You require the `trc.war` file that can be obtained by using the additional setup utility to extract the server installation media.

 **Note:**

1. The heap size must be set to at least 512 MB for this type of installation.

To deploy the server application, complete the following steps:


1. Extract the `trc.war` file by using the additional setup utility. For details about the files that are required and for running this utility, see [Utility for extracting the component installation files \(on page 111\)](#).
2. In the WebSphere administrative console complete the following steps:
 - a. Select **Applications > New Applications**.

- b. Click **New Enterprise Application**.
- c. Click browse and type the path to the **trc.war** file in a local or remote file system. Click **Next**.
- d. On the **Preparing for the application installation** screen, select **Fast path**. Click **Next**
- e. **Step 1: Installation options**
The default options can be left. The application name can be changed to something more descriptive but it must not contain any spaces. Click **Next**.
- f. **Step 2: Map modules to servers**
Leave the default association to the server. Click **Next**.
- g. **Step 3: Map virtual hosts for Web modules**
The default association to the default_host, virtual host can be changed. Click **Next**.
- h. Step 4
Use `/trc` as the context root, otherwise further changes must be made in the `trc.properties` file. Click **Next**.
- i. Step 5
A summary of the chosen deployment settings is displayed before the installation of the BigFix Remote Control application proceeds.

Click **Finish**

A status page for the installation in progress and the outcome when the installation is finished is displayed.
- j. Click **Save** to save to the master configuration.

The BigFix Remote Control application is displayed in the list of Enterprise Applications with the descriptive name that you entered in the Installation options step of the deployment process. Before you start the application, you can customize the `trc.properties` file and change the default values. The properties files are deployed with the application and are in the `installedApps` directory within WebSphere. For more information about the properties in the files, see the *BigFix Remote Control Administrator's Guide*.

 **Note:** Ensure that the correct server IP address or server name is set in the **URL** field in the **trc.properties** file, so that the targets connect to the correct server. If you are using HTTPS, the host name or IP address that is set in the URL property must exactly match the value of the **CN** field of the SSL certificate that is installed on the server.

Installing from the BigFix console

You can create and run a server installation task to install the server by using the BigFix console. For more information, see the *BigFix Remote Control Console User's Guide* and the chapter about Managing target and server configuration.

Install the target

The BigFix Remote Control target can be installed on every computer that you want to control remotely. You can also use it to start a remote control session over the internet, by using a broker to make the connection.

BigFix Remote Control provides two ways to install the target component. If you have access to the BigFix console, use the deployment fixlets to deploy the target. For more information, see the *BigFix Remote Control Console User's Guide*. Alternatively use the BigFix Remote Control target installation files.

Installing the Windows target

The `trc_target_setup.exe` file is required to install the BigFix Remote Control target component on a Windows system.

For details of how to obtain the Windows component installation files see, [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

1. Run the `trc_target_setup.exe` file.
2. Click **Next** at the welcome screen.
3. Accept the license agreement. Click **Next**.
4. Accept the default location for the installation files, or click **Change** to select a different location.
5. Specify the host name of the BigFix Remote Control server that the target connects to.
For example, `trcserver.example.com`.

 **Note:** Select **Use secure connections (https)** if you selected to use HTTPS during the server installation.

6. On the **Server Address** window, for secure target registration, enter or paste the **Registration** token.

Ensure that **Use secure connections (https)** is also selected. For more information about secure target registration, see [Add a token for secure target registration \(on page 115\)](#)

7. For advanced settings, click **Advanced settings**

Server port

The port must match the value that is entered for the **Server port on Webserver** parameter during the server installation.

Server Context

The server context is used as part of the URL for contacting the server. It must match the value that is entered after the '/' in the **Path to URL** field, on the **Web server parameters** screen during the server installation.

Use a FIPS certified cryptographic provider

Select this option to enable FIPS compliance on the target. For more information about enabling FIPS compliance, see [Enable FIPS compliance on the target \(on page 159\)](#).


Enable NIST SP800-131A compliance (Enables FIPS)

Select this option to enable NIST SP800-131A compliance on the target. For more information about enabling NIST SP800-131A compliance, see [NIST SP800-131A compliance in BigFix Remote Control \(on page 163\)](#).

8. Click **Next**.


9. On the **Proxy settings** screen if you are not using a proxy server, click **Next**.

- To use a Proxy, select **Use a proxy server or a Remote Control Gateway**.
 - a. Type in the IP address or host name for the Proxy server.
 - b. Type in the port that proxy server is listening on.
 - c. Select whether you are using an HTTP proxy or a Remote Control Gateway.
 - d. Select **Proxy requires authentication** if you must authenticate with the proxy server. Enter the ID and password for authenticating to the proxy server. The user ID and password are automatically encrypted when the target starts. For more information about the automatic passphrase encryption, see the *BigFix Remote Control Administrator's Guide*.

 **Note:** When you rerun the target installer and select **Modify** after the user ID and password are encrypted, the encrypted user ID and password combination is displayed in the user ID field. The password field remains empty.

- e. Click **Next**.

10. Accept or change the port value to be used to listen for incoming remote control sessions. Click **Next**

 **Note:** Your operating system might have a firewall that is installed by default. The inbound firewall rule for target port defaults to 888. Incoming TCP connections to that port must be open. If another port is configured instead for the BigFix Remote Control sessions, the same applies. Also, traffic on the localhost loopback address 127.0.0.1 between `trc_base`, `trc_gui`, and `trc_dsp` on arbitrary ports must be allowed.

11. To enable failover to peer-to-peer mode, select one of the following options:

Regardless of server status

A peer to peer session can be established between a controller and this target directly if the server is available or not. Click **Peer to Peer** policies to set the local policies for the target to use during a peer to peer session. Click **Next** to move through the peer to peer policies screens.

Only when server is down or unreachable

A peer to peer session can be established only if the server is down or the target cannot connect to the server. Click **Peer to Peer** policies to set the local policies for the target to use during a peer to peer session. Click **Next** to move through the peer to peer policies screens.

Never

A peer to peer session is not allowed directly between a controller and this target. If you select this option, continue from step [12 \(on page 81\)](#).

Peer to Peer policies

Session policies options

Table 9. Session policies options.

Installation option.	Target Property.	Default Value.	Description
Active	AllowActive	Selected.	<p>Determines whether the target can take part in active peer to peer sessions. For more information about the different types of remote control session that can be started, see the <i>BigFix Remote Control Controller User's Guide</i>.</p> <p>Selected.</p> <p>The target can take part in active peer to peer sessions and the Active option is avail-</p>

Installation	Default		Description
option.	Target Property.	Value.	
Guidance	AllowGuidance	Selected.	<p>able in the session type list in the controller window. The Open connection window also displays an Active option.</p> <p>Not selected.</p> <p>The target cannot take part in active peer to peer sessions and the Active option is not available in the session type list in the controller window.</p>
			<p>Determines whether the target can take part in guidance peer to peer sessions. For more information about the different types of remote control session that can be started, see the <i>BigFix Remote Control Controller User's Guide</i>.</p> <p>Selected.</p> <p>The target can take part in guidance peer to peer sessions and the Guidance option is available in the session type list in the controller window. The Open connection window also displays a Guidance option.</p> <p>Not selected.</p> <p>The target cannot take part in guidance peer to peer sessions and the Guidance option is not available in the session type list in the controller window.</p>
Monitor	AllowMonitor	Selected.	<p>Determines whether the target can take part in monitor peer to peer sessions. For more information about the different types of remote control session that can be started, see the <i>BigFix Remote Control Controller User's Guide</i>.</p> <p>Selected.</p> <p>The target can take part in monitor peer to peer sessions and the Monitor option is available in the session type list in the con-</p>

Installation	Target Property.	Default	Description
option.		Value.	
Enable high quality colors	EnableTrueColor	Not selected.	<p>troller window. The Open connection window also displays a Monitor option.</p> <p>Not selected.</p> <p>The target cannot take part in monitor peer to peer sessions and the Monitor option is not available in the session type list in the controller window.</p>
Enable true color	EnableTrueColor	Not selected.	<p>Determines whether the target desktop is displayed in high-quality colors in the controller window at the start of a session. Used together with Lock color quality.</p> <p>Selected.</p> <p>The target desktop is displayed in true color 24-bit mode at the start of the session. Partial screen updates are also enabled.</p> <p>Not selected.</p> <p>The target desktop is displayed in 8-bit color mode at the start of the session. Partial screen updates are also enabled. This value is the default value.</p>
Enable true color	EnableTrueColor	Not selected.	<p>Determines whether true color is used as the initial color depth to display the target desktop, in the controller window at the start of a session. Used along with Lock color depth.</p> <p>Selected.</p> <p>The target desktop is displayed in true color 24-bit mode at the start of the session.</p> <p>Not selected.</p> <p>The target desktop is displayed in 8-bit color mode at the start of the session. This value is the default value.</p>

Installation	Target Property.	Default	Description
option.	Target Property.	Value.	Description
Lock color quality	LockColorDepth	Not selected.	<p>Determines whether the color quality that a remote control session is started with can be changed during the session. Used together with Enable high quality colors.</p> <p>Selected.</p> <p>The initial color quality, for the remote control session, is locked and cannot be changed during the session. The Performance settings icon is disabled in the controller window. The controller user cannot change settings to improve the session performance if their network is slow.</p> <p>Not selected.</p> <p>The color quality can be changed during the session. The Performance settings icon is enabled in the controller window.</p>
Lock color depth	LockColorDepth	Not selected.	<p>Determines whether the color depth that a remote control session is started with can be changed during the session. Used along with Enable true color.</p> <p>Selected.</p> <p>The initial color depth, for the remote control session, is locked and cannot be changed during the session. The Enable true color icon is disabled in the controller window.</p> <p>Not selected.</p> <p>The initial color depth can be changed during the session.</p>
Remove desktop background	RemoveBackground	Not selected.	<p>If the target has a desktop background image set, this property can be used to remove the background from view during a remote control session.</p> <p>Selected.</p>

Installation option.	Target Property.	Default Value.	Description
			<p>The desktop background image on the target is not visible during a remote control session.</p> <p>Not selected.</p> <p>The desktop background image on the target is visible during a remote control session.</p>
Stop screen saver updates when screen saver is active	NoScreenSaver	Not selected.	<p>Stops the target from sending screen updates when it detects that the screen saver is active.</p> <p>Selected.</p> <p>While the screen saver is active on the target system, the target stops transmitting screen updates. The controller displays a simulated screen saver, so that the controller user is aware that a screen saver is active on the remote display. The controller user can remove the screen saver by pressing a key or moving the mouse.</p> <p>Not selected.</p> <p>A simulated screen saver is not displayed in the session window. The target screen is displayed as normal and the target continues to transmit screen updates.</p>

Policies options

Table 10. Peer to peer policy descriptions -

Installer screen names.	Target property.	Default value.	Description
Disable chat	DisableChat	Not selected.	Determines whether you can start a chat session with the target and also chat to the controller user during a peer to peer session.

Installer	screen	Default	Description
names.	Target property.	value.	Description
Save chat messages	AutoSaveChat	Not selected.	<p>Selected.</p> <p>If ChatOnly is chosen as the connection type on the open connection screen, the session is refused. During the session, the chat icon is not available in the controller window.</p> <p>Not selected.</p> <p>A Chat Only session can be started from the open connection window. During the session, the chat icon is available in the controller window.</p> <p>Determines whether the chat messages that are entered during a chat session are saved.</p>
Disable file transfer from target to controller	DisableFilePull	Not selected.	<p>Selected.</p> <p>The chat messages are saved in an html file, in the working directory of the target. The location is defined by the target property WorkingDir. The file name is prefixed with <i>chat-</i>. For example, on a Windows system, a file that is named <code>chat-m15.html</code> is saved to the following location.</p> <pre data-bbox="883 1335 1300 1444">c:\Documents and Settings\All Users\Application Data\IBM\Tivoli\Remote Control</pre> <p>Not selected.</p> <p>The chat messages are not saved to a file.</p> <p>Determine whether files can be transferred from the target to the controller during the session.</p> <p>Selected.</p> <p>Files can be transferred from the target to the controller.</p> <p>Not selected.</p>


Installer screen names.	Target property.	Default value.	Description
Disable file transfer from controller to target	DisableFilePush	Not selected.	Files cannot be transferred from the target to the controller. Determines whether files can be transferred from the controller to the target during the session. Selected. Files can be transferred from the controller to the target. Not selected. Files cannot be transferred from the controller to the target.
Disable clipboard transfer	DisableClipboard	Not selected.	Determines the availability of the clipboard transfer menu. Use this menu option to transfer the clipboard content between the controller and target during a remote control session. Selected. The clipboard transfer menu is available during the session and you can transfer the clipboard content to and from the target. Not selected. The clipboard transfer menu is not available during the session.
Allow local recording	AllowRecording	Selected.	Determines whether the controller user can make and save a local recording of the session in the controlling system. Determines the availability of the record option on the controller window. For more information about recording sessions, see the <i>BigFix Remote Control Controller User's Guide</i> . Selected. The record option is available in the controller window.

Installer screen names.	Target property.	Default value.	Description
Allow collaboration	AllowCollaboration	Selected.	<p>Not selected.</p> <p>The record option is not available in the controller window.</p> <p>Determines whether more than one controller can join a session. Determines the availability of the collaboration icon on the controller window. For details of collaboration sessions, see the <i>BigFix Remote Control Controller User's Guide</i>.</p> <p>Selected.</p> <p>The collaboration icon is available in the controller window.</p> <p>Not selected.</p> <p>The collaboration icon is not available in the controller window.</p>
Allow session handover	AllowHandover	Selected.	<p>Determines whether the master controller in a collaboration session can hand over control of the session to a new controller. Determines the availability of the Handover button on the collaboration control panel. For more information about collaboration sessions, see the <i>BigFix Remote Control Controller User's Guide</i>.</p> <p>Selected.</p> <p>The handover option is available in the collaboration control window.</p> <p>Not selected.</p> <p>The handover option is not available in the collaboration control window.</p>
Allow requests to disconnect existing session	AllowForceDisconnect	Not selected.	<p>Determines whether a controller user is given the option to disconnect a session with a target so that they can connect to the target instead. Used with the Managed and CheckUserLogin properties. For more information about</p>


Installer	screen	Default	Description
names.	Target property.	value.	Description
			<p>disconnecting sessions, see the <i>BigFix Remote Control Controller User's Guide</i>.</p> <p>Selected.</p> <p>A Disconnect session option is available in the message window that is displayed when you attempt to connect to the target.</p> <p>Not selected.</p> <p>A Disconnect session option is not available when you attempt to connect to the target.</p> <p>The CheckUserLogin property must be set to Yes and Managed set to No for AllowForceDisconnect to take effect.</p>
Disconnect grace time	ForceDisconnect-Timeout	45	<p>Number of seconds in which the current controller user must respond to the prompt to disconnect the current session. If they do not respond on time, they are automatically disconnected from the session. The timer takes effect only when AllowForceDisconnect and CheckUserLogin are set to Yes. The default value is 45.</p>
Audit to Application Event Log	AuditToSystem	Selected.	<p>Determines whether the actions that are carried out during remote control sessions are logged to the application event log on the target. This log can be used for audit purposes.</p> <p>Selected.</p> <p>Entries are displayed in the application event log of the target corresponding to each action carried out during the session.</p> <p>Not selected.</p> <p>No entries are logged to the application event log.</p>


Security policies



Table 11. Peer to peer policy descriptions - Security policies.

Installer screen names.	Target property.	Default Value.	Description.
Authenticate by using Windows logon	CheckUserLogin	Selected.	<p>Determines whether a logon window is displayed when the controller user clicks a session type button on the Open Connection window.</p> <p>Yes</p> <p>The logon window is displayed and the controller user must log on with a valid Windows ID and password. If the credentials are invalid, the target refuses the session.</p> <p>No</p> <p>The user acceptance window does not appear and the peer to peer session is established.</p>
Must be a member of these Windows groups	CheckUserGroup	See description.	<p>Default value.</p> <p>Windows systems.</p> <div data-bbox="938 1104 1308 1157" style="background-color: #f0f0f0; padding: 2px;"> <p>BUILTIN\Administrators</p> </div> <p>Linux systems.</p> <div data-bbox="938 1220 1308 1272" style="background-color: #f0f0f0; padding: 2px;"> <p>wheel</p> </div> <p>When Authorized user group has a value set, the user name that is used for authentication must be a member of one of the listed groups. Otherwise, the session is refused. Multiple groups must be separated with a semicolon. For example, <code>wheel;trcusers</code>.</p> <p> Note: By default, on a Windows system, only the administrator user is granted access. On a Linux system, by default no users are granted access. To resolve this issue, complete one of the following steps.</p> <ol style="list-style-type: none"> a. If the users must also be granted administrator rights, add them as members of the Administra-

Installer	Target property.	Default	Description.
screen names.		Value.	<p>tors group on a Windows system or the wheel group on a Linux system.</p> <p>b. If the users must not have administrator rights, complete the following steps.</p> <p>i. Create a group or use an existing group. For example, the following command might be run as root:</p> <pre>groupadd trcusers</pre> <p>ii. Add the users to this group. For example, the following command might be run as root to add <i>bsmith</i> to <i>trcusers</i>.</p> <pre>usermod -a -G trcusers <bsmith></pre> <p>iii. Add the group to the list in the Authorized user group field.</p>
Allow privacy	AllowPrivacy	Selected.	<p>Determines whether a controller user can lock the local input and display of the target when in a remote control session. Determines the visibility of the Enable Privacy option on the controller window.</p> <p>Selected.</p> <p>The Enable Privacy option is available in the Perform Action in target menu in the controller window.</p> <p>Not selected.</p> <p>The Enable Privacy option is not available in the Perform Action in target menu in the controller window.</p>
Allow input lock	AllowInputLock	Selected.	<p>This property works with Allow privacy and on its own. Select Allow input lock to lock the target users mouse and keyboard during a remote control session.</p> <p>Selected.</p>

Installer		Default	Description.
screen names.	Target property.	Value.	
<p>Enable privacy when session starts</p>	<p>EnablePrivacy</p>	<p>Not selected.</p>	<p>The lock target input menu item is enabled, in the Perform action in target menu in the controller window. Select lock target input to lock the target users mouse and keyboard during a remote control session. The target screen is still visible to the target user.</p> <p>Not selected.</p> <p>The lock target input menu item is not enabled in the Perform action in target menu in the controller window.</p> <p> Note: If Enable Privacy is selected during a session, the remote user input is automatically locked. It is not possible to enable privacy without also locking the input.</p>
			<p>Determines whether the local input and display are locked for all sessions. Therefore, the target user cannot interact with the target screen during a remote control session.</p>
			<p>Selected.</p>
			<p>The target screen is blanked out by the privacy bitmap when the session starts. The target user cannot interact with the screen during the session. The target desktop is still visible to the controller user in the controller window.</p>
			<p>Not selected.</p>
			<p>The target screen is not blanked out when the session starts and the target user can interact with the screen.</p>


Installer	Target property.	Default	Description.
screen names.	Target property.	Value.	Description.
Enable input lock when session starts	EnableInputLock	Not selected.	<p>This property works with Enable privacy. Use Enable input lock to determine whether the target user can view their screen or not during a remote control session when privacy mode is enabled.</p> <p>Selected.</p> <p>The target screen is visible to the target user during the session, while in privacy mode but their mouse and keyboard control is locked.</p> <p>Not selected.</p> <p>The target screen is not visible to the target user and the privacy bitmap is displayed on the target during the session. The target users mouse and keyboard are also disabled.</p> <p> Note: Enable privacy must be selected to allow Enable input lock to take effect.</p>
Enable on-screen session notification	EnableOSSN	Not selected.	<p>Determines whether a semi-transparent layer is placed onto the target screen. The layer displays text that indicates that a remote control session is in progress. Can be used when privacy is a concern so that the user is clearly notified when somebody remotely views or controls their PC.</p> <p>Selected.</p> <p>The semi-transparent layer is displayed on the target screen. The text indicates which type of remote control session is in progress. For example : BigFix Remote Control - Active Mode. The layer does not intercept keyboard or mouse actions. Therefore, the user is still able to interact with their screen.</p>


Installer	Target property.	Default	Description.
screen names.		Value.	<p>Not selected.</p> <p>A semi-transparent layer is not displayed on the target screen.</p> <p> Note: This policy is only supported on targets where a Windows operating system is installed.</p>
Disable Panic Key	DisablePanicKey	Not selected.	<p>Determines whether the target user can use the Pause Break key to automatically end the remote control session.</p> <p>Selected.</p> <p>The target user cannot use the Pause Break key to automatically end the remote control session.</p> <p>Not selected.</p> <p>The target user can use the Pause Break key to automatically end the remote control session.</p>
Inactivity timeout	IdleTimeout	360	<p>Number of seconds to wait until the connection ends if there is no session activity. Set this value to 0 to disable the timer so that the session does not end automatically. The minimum timeout value is 60 seconds. For values 1 - 59, the session times out after 60 seconds of inactivity.</p> <p> Note: The inactivity timeout value applies to Active session mode only. The session does not end automatically when other session modes are used.</p> <p>The default value is 360.</p>


User acceptance policies

Table 12. Peer to peer policy descriptions - User acceptance policies.

Installer screen names.	Target property.	Default Value.	Description.
Take over session	ConfirmTakeOver	Selected.	<p>Determines whether the user acceptance window is displayed when a remote control session is requested.</p> <p>Selected.</p> <p>The user acceptance window is displayed to the target user who can accept or refuse the session.</p> <p>Not selected.</p> <p>The user acceptance window is not displayed and the session is established.</p>
Change session mode	ConfirmModeChange	Selected.	<p>Determines whether the user acceptance window is displayed when the controller user selects a different session mode from the session mode list on the controller window.</p> <p>Selected.</p> <p>The user acceptance window is displayed each time a session mode change is requested. The target user must accept or refuse the request.</p> <p>Not selected.</p> <p>The user acceptance window is not displayed and the session mode is changed automatically.</p>
File transfers	ConfirmFileTransfer	Selected.	<p>Determines whether the user acceptance window is displayed when the controller user transfers files between the target and the controller.</p> <p>Selected.</p> <p>The acceptance window is displayed when the following options are selected.</p>

Installer		Default	Description.
screen names.	Target property.	Value.	
			<p>The target user must accept or refuse the file transfer.</p> <ul style="list-style-type: none"> The controller user selects pull file from the file transfer menu on the controller window. <p> Note: After they accept the request, the target user must select the file that is to be transferred.</p> <ul style="list-style-type: none"> The controller user selects send file to controller from the Actions menu in the target window.
			<p>Not selected.</p> <p>The acceptance window is not displayed and files are transferred automatically from the target to the controller system when requested.</p>
System information	ConfirmSysInfo	Selected.	<p>Determines whether the user acceptance window is displayed when the controller user requests to view the target system information.</p> <p>Selected.</p> <p>The user acceptance window is displayed when the controller user clicks the system information icon in the controller window. The target user must accept or refuse the request to view the target system information.</p> <p>Not selected.</p> <p>The target system information is displayed automatically when the controller user clicks the system information icon.</p>
Local recording	ConfirmRecording	Selected.	<p>Determines whether the user acceptance window is displayed when the controller user clicks the record icon on the controller window.</p>

Installer		Default	Description.
screen names.	Target property.	Value.	Description.
			<p>Selected.</p> <p>A user acceptance window is displayed when the controller user clicks the record icon on the controller window. If the target user clicks Accept, the controller user can select where to save the recording to. If the target user clicks Refuse, a refusal message is displayed to the controller.</p> <p> Note: After the target user accepts the request for recording, the acceptance window is not displayed again if the controller user stops and then restarts local recording in the same session. Also, the refusal message is displayed in English and is not translated.</p> <p>Not selected.</p> <p>When the controller user clicks the record icon on the controller window, the user acceptance window is not displayed. The controller user can then select where to save the recording to.</p>
Collaboration	ConfirmCollaboration	Selected.	<p>Determines whether the user acceptance window is displayed when another controller user requests to join a collaboration session with a target.</p> <p>Selected.</p> <p>The user acceptance window is displayed when the controller user tries to join the collaboration session. The target user must accept or refuse the request. If the target user clicks Accept, the additional controller joins the collaboration session. If they click Refuse, a</p>

Installer		Default	Description.
screen names.	Target property.	Value.	
			<p>message is displayed on the controller and the additional controller cannot join the collaboration session.</p> <p>Not selected.</p> <p>The additional controller automatically joins the collaboration session.</p>
User acceptance grace time	AcceptanceGraceTime	45	<p>Sets the number of seconds to wait for the target user to respond before a session starts or times out. Used with Take over session.</p> <ul style="list-style-type: none"> • Acceptable values 0 - 60 - If set to 0 the activity starts without displaying the message box for user acceptance on the target. <p> Note: If Take over session is selected, User acceptance grace time must be set to a value >0 to allow the target user time to respond.</p>
Proceed on acceptance timeout	AcceptanceProceed	Not selected.	<p>Continue with the session if the user acceptance timeout lapses. The target user does not click accept or refuse within the number of seconds defined for Acceptance grace time.</p> <p>Selected.</p> <p>The session starts.</p> <p>Not selected.</p> <p>The session does not start.</p>
Do not prompt for user acceptance when user is not logged on.	AutoWinLogon	Selected.	<p>Determines whether a session can be started when no users are logged on at the target. Determines whether the user acceptance window is displayed on the target, at session start, when the target user is not logged on.</p> <p>Selected.</p> <p>Session is started with the target. The acceptance window is not displayed</p>

Installer	Target property.	Default Value.	Description.
			on the target and the session is established.
			Not selected. Session is not started and the following message is displayed. <i>Session rejected because there is no user logged to confirm the session</i> The session is refused because the target user is not logged on and therefore cannot accept the session request.
Enable Hide windows	HideWindows	Not selected.	Determines whether the Hide windows check box is displayed on the user acceptance window when Confirm incoming connections is also selected. Selected. The Hide windows check box is displayed on the user acceptance window. Not selected. The Hide windows check box is not displayed on the user acceptance window.

Session scripts

Table 13. Peer to peer policy descriptions - Session scripts policies.

Installer	Target property.	Default Value.	Description.
Run pre-session script	RunPreScript	Not selected.	Determines whether a user-defined script must be run before the remote control session starts. It is run just after the session is authorized but before the controller user has access to the target. The outcome of running the script and the continuation of the session is determined by the value set for Proceed on pre/post-script failure . Selected.

Installer		Default	Description.
screen names.	Target property.	Value.	
			<p>When a remote control session is requested, the defined script is run before the controller user has access to the target.</p>
			<p>Not selected.</p>
			<p>No script is run before the session.</p>
			<p>For details of setting up pre-session scripts and post session scripts, see the Session policies chapter in the <i>BigFix Remote Control Administrator's Guide</i>.</p>
<p>Run post-session script</p>	<p>RunPostScript</p>	<p>Not selected.</p>	<p>Determines whether a user-defined script is run after the remote control session finishes.</p>
			<p>Selected.</p>
			<p>When a remote control session ends, the user-defined script is run.</p>
			<p>Not selected.</p>
			<p>No script is run after the session.</p>
			<p>For details of setting up pre and post session scripts, see the Session policies chapter in the <i>BigFix Remote Control Administrator's Guide</i>.</p>
<p>Proceed with session when script fails</p>	<p>ProceedOnScript-Fail</p>	<p>Not selected.</p>	<p>Continue with the session if the pre-script or post script execution fails. A positive value or 0 is considered a successful run of the pre-script or post session script. A negative value, a script not found error, or a script that does not finish within 3 minutes is considered a failure.</p>
			<p>Selected.</p>
			<p>If the pre-script or post script run fails, the session continues.</p>
			<p>Not selected.</p>

Installer screen names.	Target property.	Default Value.	Description.
			If the pre-script or post script run fails, the session does not continue ends immediately.

For the definition and more information about the properties, see [Properties that can be set in the target configuration \(on page 196\)](#).

Session policies options

Table 14. Session policies options.

Installation option.	Target Property.	Default Value.
Active	AllowActive	Selected.
Guidance	AllowGuidance	Selected.
Monitor	AllowMonitor	Selected.
Enable high quality colors	EnableTrueColor	Not selected.
Enable true color	EnableTrueColor	Not selected.
Lock color quality	LockColorDepth	Not selected.
Lock color depth	LockColorDepth	Not selected.
Remove desktop background	RemoveBackground	Not selected.
Stop screen saver updates when screen saver is active	NoScreenSaver	Not selected.

Policies options

Table 15. Policy descriptions -

Installer screen names.	Target property.	Default value.
Disable chat	DisableChat	Not selected.
Save chat messages	AutoSaveChat	Not selected.
Disable file transfer from target to controller	DisableFilePull	Not selected.

Installer screen names.	Target property.	Default value.
Disable file transfer from controller to target	DisableFilePush	Not selected.
Disable clipboard transfer	DisableClipboard	Not selected.
Allow local recording	AllowRecording	Selected.
Allow collaboration	AllowCollaboration	Selected.
Allow session handover	AllowHandover	Selected.
Allow requests to disconnect existing session	AllowForceDisconnect	Not selected.
Disconnect grace time	ForceDisconnectTimeout	45
Audit to Application Event Log	AuditToSystem	Selected.

Security policies

Table 16. Security policies.

Installer screen names.	Target property.	Default Value.
Authenticate by using Windows logon	CheckUserLogin	Selected.
Must be a member of these Windows groups	CheckUserGroup	See description.
Allow privacy	AllowPrivacy	Selected.
Allow input lock	AllowInputLock	Selected.
Enable privacy when session starts	EnablePrivacy	Not selected.
Enable input lock when session starts	EnableInputLock	Not selected.
Enable on-screen session notification	EnableOSSN	Not selected.
Disable Panic Key	DisablePanicKey	Not selected.
Inactivity timeout	IdleTimeout	360

User acceptance policies

Table 17. User acceptance policies.

Installer screen names.	Target property.	Default Value.
Take over session	ConfirmTakeOver	Selected.

Installer screen names.	Target property.	Default Value.
Change session mode	ConfirmModeChange	Selected.
File transfers	ConfirmFileTransfer	Selected.
System information	ConfirmSysInfo	Selected.
Local recording	ConfirmRecording	Selected.
Collaboration	ConfirmCollaboration	Selected.
User acceptance grace time	AcceptanceGraceTime	45
Proceed on acceptance timeout	AcceptanceProceed	Not selected.
Do not prompt for user acceptance when user is not logged on.	AutoWinLogon	Selected.
Enable Hide windows	HideWindows	Not selected.

Session scripts

Table 18. Session scripts policies.

Installer screen names.	Target property.	Default Value.
Run pre-session script	RunPreScript	Not selected.
Run post-session script	RunPostScript	Not selected.
Proceed with session when script fails	ProceedOnScriptFail	Not selected.


Additional Features

Select **Install device driver for Virtual Smart Card Reader** to install the virtual smart card reader driver. For more information about the smart card reader driver, see [Install a driver to support smart card authentication in the target \(on page 121\)](#).

12. Click **Install** to begin the installation.
13. When the installation is complete, click **Finish**.


Installing the Linux target


You can install the target component on a Linux computer by using the RPM file that is provided in the BigFix Remote Control installation files.

 **Note:** The target, CLI, gateway, and broker component installation packages depend on the 32-bit version of the following libraries. For all components, **glibc** and **libblkid**. Also, for the target component, **libgcc**, **libXmu**, **libXtst**, **libXp**, **libXi**, **libXScrnSaver**, and **libXinerama**. Therefore, you must ensure that the libraries are installed.

Use the `ibm-trc-target-9.x.x.i386.rpm` file to install the target component in Linux, where 9.x.x is the version that you want to install. For more information about how to obtain the Linux component installation files, see [Obtain the installation files \(on page 22\)](#). Choose the appropriate method for obtaining the file.

Install a default target RPM file and then configure the target after the installation.

 **Note:** If you are using Red Hat Enterprise Linux 6.0 64-bit the following libraries along with their dependencies, need to be installed if they are not already installed, **glibc.i686**, **libgcc.i686**, **libXmu.i686**, **libXtst.i686**, **libXp.i686**, **libXi.i686**, **libXScrnSaver.i686**.

 **Note:** The installation package depends on the 32-bit version of the following libraries, **glibc**, **libgcc**, **libXmu**, **libXtst**, **libXp**, **libXi**, **libXScrnSaver**, **libXinerama**, and **libblkid**. Therefore, you must ensure that the libraries are installed.

To install the RPM file, run the following command and use the file specific to the version that you want to install. For example,

```
rpm -ivh ibm-trc-target-9.1.2.i386.rpmrpm -ivh ibm-trc-target-9.1.3.i386.rpmrpm -ivh ibm-trc-target-9.1.4.i386.rpm
```

When the target is installed, configure the target properties by editing the `/etc/ibmtrct.conf` file. For more information about target properties and their definitions, see [Installing the Windows target \(on page 57\)](#)[Properties that can be set in the target configuration \(on page 196\)](#).


Install the BigFix Remote Control Target for macOS

You can install the BigFix Remote Control Target for macOS in numerous ways. Use the `trc_target.pkg` file to install the application in attended or unattended mode. You can also install the target by using a Fixlet® in the BigFix console.

For information about how to obtain the BigFix Remote Control Target for macOS component installation files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

Installing the BigFix Remote Control Target for macOS from the BigFix console

You can use a Fixlet in the BigFix console to install the BigFix Remote Control Target for macOS component. The deployment Fixlet is available in the Remote Control site in the Systems Lifecycle domain.

 **Note:** An option to select managed mode, which prompts for a server URL and a secure registration token, is not available because managed mode is not supported on the BigFix Remote Control Target for macOS.

To install the BigFix Remote Control Target for macOS target component, complete the following steps.

1. Within the **Systems Lifecycle** domain, expand **Remote Control configuration > Remote Control**.
2. Expand the **Deployment** node.
3. Select **macOS**.
4. Select **Deploy BigFix Remote Control Target for macOS**.
5. In the **Task** pane, review the description and follow the instructions in the **Actions** box to start the task.
6. In the **Take Action** pane on the **Target** tab, select the relevant option for determining the computers on which to deploy the BigFix Remote Control Target for macOS component.
7. Click **OK**.
The summary screen shows the progress of the task and the status is set to **Complete** when it is finished.

Installing the BigFix Remote Control Target for macOS by using the .pkg file

You can use the `trc_target.pkg` file to install the BigFix Remote Control Target for macOS.

You can obtain the `pkg` file from Passport Advantage or from the BigFix Remote Control server UI. For more information, see [Obtain the installation files \(on page 22\)](#). Two installation methods can be used when you have the `pkg` file: attended and unattended.

You can also apply custom configuration settings when you install the target. The configuration values are set in the `trc_target.cfg` file. Create the file and add your custom values. Copy the file to

the computers on which you want to install the BigFix Remote Control Target for macOS. Copy the `trc_target.cfg` file to the same directory as the `trc_target.pkg` file.

Your configuration settings are installed together with the target. The target configuration is installed to `/Library/Preferences/com.ibm.bigfix.remotecontrol.target.plist`.

To configure the target to support broker sessions, you must configure the **BrokerList** property and provide trusted certificates. Place a `broker.certs` file, that contains the trusted certificates in the same directory as the `trc_target.pkg` file. The package installs the `broker.certs` file to

`/Library/Application Support/com.ibm.bigfix.remotecontrol.target/TrustStore`.

For more information about the target properties that can be set in the `.cfg` file, see [Properties that can be set in the target configuration \(on page 196\)](#).

If you do not apply any custom configuration, the target uses built in configuration settings when it installs.

Choose an installation method for installing the BigFix Remote Control Target for macOS.

Attended Mode:

1. Double-click the `trc_target.pkg` file.
2. Click **Continue**.
3. Click **Install** to install to the startup disk. If your system has multiple disks, you can select the disk on which to install the target. Click **Change Install Location** to select an installation disk.
4. If you are a user with admin authority, type in your password when prompted. Otherwise, type a valid admin ID and password. Click **Install Software**.
5. When the installation completes, click **Close**.

Unattended mode:

1. Open a **Terminal** window and type the following command.

```
sudo installer -pkg "[path]/trc_target.pkg" -target /
```

Where `[path]` is the path to the `.pkg` file.

After you install the `.pkg` file, open the `Remote Control Target.app` to start the target.

Run a target custom installation

Run an BigFix Remote Control target custom installation to install the target software by using parameters. You can run the installation in multiple ways.

Unattended and silent

No interaction is required by the user and no UI dialogs or progress bars are displayed to the user.

Unattended

No interaction is required by the user and an installation progress bar is displayed to the user.

Attended

The full installation UI is displayed and requires user interaction.

You can customize installation settings and also assign the target to a specific group during the installation.

Running a target custom installation on a Windows system

To install the target software on a Windows operating system, use the `trc_target_setup.exe` file.

For more information about obtaining this file, see [Obtain the installation files \(on page 22\)](#).


To install the target, complete the following steps:

1. Create a folder in your root drive called `IBMTRC`.
2. Copy `trc_target_setup.exe` to `IBMTRC`.
3. Open a command prompt window and go to `IBMTRC`.
4. Type `DIR` to verify that the `exe` file is in this folder.
- 5.

To install the target, type the following command in one line.

```
trc_target_setup.exe /s /v"/qn [INSTALLPARAMETER1][INSTALLPARAMETER2]...[INSTALLPARAMETERX]"
```

Use the following installation parameters customize your installation.

 **Note:** Ensure that the correct values are assigned to the parameters as no validation of the values is carried out.

`/s`

Denotes a silent installation.

`/v"`

The string that is attached to `/v` contains the parameters for `msiexec.exe`, which is a piece of software that runs the installation.

/qn

Run a silent and unattended installation with no progress window and no UI.

You can also replace `/qn` with the following parameters.

/qb

For an unattended installation with a basic UI and a small progress bar.

/qr

For an unattended installation with a reduced UI progress bar in a large window.

/qf

For an attended installation with full UI.

TRC_SERVER_HOSTNAME

The host name or IP address of the server. This property is required. Default value is *<blank>*.

For example, `TRC_SERVER_HOSTNAME=trc.myserver.com`.

TRC_SERVER_CONTEXT

This parameter value must match the last part of the path in the server URL. Default value is *trc*.

For example, `TRC_SERVER_CONTEXT=trc`.

TRC_SERVER_PORT

If the server runs on a non-standard port, specify the port number. Default value is 80.

For example, `TRC_SERVER_PORT=8080`.

TRC_SERVER_PROTOCOL

Choose between plain HTTP and secure HTTPS protocols. Valid values are `http` and `https`. Default value is `http`.

For example, `TRC_SERVER_PROTOCOL=http`.

TRC_PROXY_HOSTNAME

Host name or IP address for the proxy server, if you are using one. Default value is *<blank>*.

For example, `TRC_PROXY_HOSTNAME=proxy.company.com`.

TRC_PROXY_PORT

Port number for the proxy server. Default value is *<blank>*.

For example, `TRC_PROXY_PORT=8080`.

TRC_PROXY_USER_ID

The user ID, if the proxy requires authentication. Default value is *<blank>*. The user ID and password are automatically encrypted when the target starts, unless **DISABLEAUTOMATICPASSPHRASEENCRYPTION** is set to *Yes*. For more information about automatic passphrase encryption, see the *BigFix Remote Control Administrator's Guide*.

For example, `TRC_PROXY_USER_ID=proxyuser`.

TRC_PROXY_PASSWORD

The password, if the proxy requires authentication. Default value is *<blank>*. The user ID and password are automatically encrypted when the target starts, unless **DISABLEAUTOMATICPASSPHRASEENCRYPTION** is set to *Yes*. For more information about automatic passphrase encryption, see the *BigFix Remote Control Administrator's Guide*.

`TRC_PROXY_PASSWORD=v264xmpt`.

TRC_PROXY_AUTH_B64

The user ID and password, format `user: password`, encoded in base64. Overrides the user ID and password properties. If you do not want the password to be easily visible, use this parameter. Base64 is not encryption. Default value is *<blank>*.

For example, `TRC_PROXY_AUTH_B64=cHJveH11c2VyOnYyNjR4bXB0`

The user ID and password are automatically encrypted when the target starts, unless **DISABLEAUTOMATICPASSPHRASEENCRYPTION** is set to *Yes*. For more information about automatic passphrase encryption, see the *BigFix Remote Control Administrator's Guide*.

TRC_TARGET_PORT

To run the target on a non-standard port, specify the port number to use. Default value is 888.

For example, `TRC_TARGET_PORT=888`.

TRC_SERVER_HEARTBEAT_RETRY

The amount of time, in minutes, that the target waits before it resends a heartbeat to the server, when the server is not responding. Default value is 10.

For example, `TRC_SERVER_HEARTBEAT_RETRY=1`.

TRC_ACCESSIBILITY

Enables the accessible UI. Default value is *No*. Available on Windows operating system.

GROUP_LABEL

The name of the group that the target is to be assigned to. To enable this feature, edit the `trc.properties` file and set `allow.target.group.override = true`. For more information about editing the properties files, see the *BigFix Remote Control Administrator's Guide*. Default value is *DefaultTargetGroup*.

Note:

- a. The GROUP_LABEL parameter is discarded if the target is already registered in the BigFix Remote Control server.
- b. The target group that is specified must already be defined on the server.

For example, `GROUP_LABEL=NewTargetGroup`.

INSTALLDIR

Use this parameter to specify the directory for installing the target software to.

For example, `INSTALLDIR= c:\trc\target`.

ALLOWP2P

Use this parameter to enable peer to peer connections regardless of the server status. Default value is *No*.

ALLOWP2PFAILOVER

Use this parameter to enable failover to peer-to-peer mode when the server is down or unreachable. Default value is *No*.

AUDITTOSYSTEM

Use this parameter to log peer to peer session events in the targets application event log for auditing purposes. Default value is *No*.

AUTOSAVECHAT

Use this parameter to save the contents of the chat window to a file on the target. Default value is *No*.

AUTOWINLOGON

Determines whether a session can be started when no users are logged on at the target. Determines whether the user acceptance window is displayed on a target where the user is not logged on. Default value is *Yes*.

CHECKUSERGROUP

The controller user must be a member of the listed groups. Default value is **BUILTIN** \Administrators on Windows systems and **wheel** on Linux systems.

CHECKUSERLOGIN

Determines whether the login window is displayed when the controller user selects a session type in the **Open Connection** window. Default value is *Yes*.

CONFIRMFILERTRANSFER

Determines whether the user acceptance window is displayed before the controller user transfer files from the target to the controller in a peer to peer session. Default value is *Yes*.

CONFIRMMODECHANGE

Determines whether the user acceptance window is displayed when the controller user selects a different session mode during the remote control session. Default value is *Yes*.

CONFIRMSYSINFO

Determines whether the user acceptance window is displayed when the controller user requests to view the target system information. Default value is *Yes*.

CONFIRMTAKEOVER

Determines whether the user acceptance window is displayed when a peer to peer session is requested. Default value is *Yes*.

DISABLEAUTOMATICPASSPHRASEENCRYPTION

Determines whether the proxy authentication user ID and password are automatically encrypted when the target starts. Default value is *No*. For more information about automatic passphrase encryption, see the *BigFix Remote Control Administrator's Guide*.

DISABLECHAT

Determines whether you can start a chat session with the target and also chat to the controller user during a peer to peer session. Default value is *No*.

DISABLECLIPBOARD

Determines the availability of the clipboard transfer menu during a peer to peer session. Default value is *No*.

DISABLEFILEPULL

Determines whether you can transfer files from the target to the controller during a peer to peer session.

DISABLEFILEPUSH

Determines whether you can transfer files from the controller to the target during a peer to peer session. Default value is *No*.

DEBUGTRACE

Enable debug logging. Debug messages are written to the target log file that can be used for problem determination. Default value is *No*.

FIPSCOMPLIANCE

Enable the use of a FIPS certified cryptographic provider for all cryptographic functions. Default value is *No*.

SP800131ACOMPLIANCE

Enable the use of NIST SP800-131A compliant algorithms and key strengths for all cryptographic functions. Default value is *No*.

HTTPSSTRICTVALIDATION

Determines whether the target uses the system truststore to verify HTTPS connections to the server. Default value is *No*.

LOGLEVEL

Set the logging level. The logging level determines the types of entries and how much information is added to the target log file. Possible values 0, 1, 2, or 4. However, use **LOGLEVEL=4** only by request from IBM software support. Default value is 2.

For example, `LOGLEVEL=2`.

LOGROTATION

Controls the period after which an older log file is overwritten. Set to **Daily**, **Weekly**, or **Monthly**. Default value is **Weekly**.

For example, `LOGROTATION=Monthly`.

You can also disable log rotation by using the value **Disabled**.


LOGROLLOVER

Controls the period after which a new log file is started. Therefore, this period must be shorter than the LOGROTATION period, not all combinations are valid. LOGROLLOVER cannot be disabled. Set to **Daily** or **Hourly**. Default value is Daily.

For example, LOGROLLOVER=Daily.

VSC


Use the parameter to install the device driver for the IBM virtual smart card reader. Add **VSC=1** to the parameter list to install the driver.

 **Note:** The appearance of **VSC** in the parameter list determines whether the driver is installed, not the value of the parameter. If **VSC= n** is in the parameter list, the driver is installed. If **VSC** is not in the parameter list, the driver is not installed. **VSC** can have any value. However, **VSC=1** is the suggested value.

For more information about installing the device driver for the IBM virtual smart card reader during a silent installation, see [Installing the virtual smart card reader driver by running a silent installation \(on page 123\)](#).

REGISTRATIONTOKEN

Use this parameter to provide the registration token to the target. The token is used to authenticate the target to the server when it first contacts the server. The value of the property is set to the registration token. For more information about installing the target with a secure registration token by running a silent installation, see [Running a target silent installation with a secure registration token \(on page 117\)](#).

 **Note:** To reconfigure the parameters on an existing target installation, use the parameter, **REINSTALL=ALL**. However, the parameter is ignored if it is used when you upgrade the target.

For example, on the command line you can type the following command:

```
trc_target_setup.exe /s /v"/qn REINSTALL=ALL"
```


To modify the target configuration and apply an upgrade, complete the following steps.

1. Perform a silent installation with the new version of target software. Do not use any parameters. If you do use parameters, the target is upgraded but the parameters are ignored and are not updated.
2. Perform a silent re installation with `REINSTALL=ALL` and any new parameters.

You can also specify the parameters that you want to override.

For example, to change the target port to 2222, type the following command.


```
trc_target_setup.exe /s /v"/qn TRC_TARGET_PORT=2222 REINSTALL=ALL"
```

 **Note:** To view Help options during the installation, type the following command on the command line.
trc_target_setup.exe --help

Installing and configuring the target using the RPM file

RPM (Red Hat Package Manager) is the most common software package manager used for Linux distributions.

The following instructions will allow you to customise and build the BigFix Remote Control target RPM file.

 **Note:** If you have the target CLI package already installed on the target you must uninstall this before installing the target software by running the following command

```
$ rpm -e ibm-trc-cli
```

Configuring the BigFix Remote Control RPM build tree

The RPM build tree is where building an RPM takes place. By default, this tree is under `/usr/src`, but this requires building as the root user. It is recommended that you create your own RPM build tree.

Use the following steps to configure the RPM build tree in `src/rpm` in your home directory.

Type the following commands to configure the RPM build tree :

1. `$ mkdir -p ~/src/rpm`
2. `$ cd ~/src/rpm`
3. `$ mkdir BUILD RPMS SOURCES SPECS SRPMS`
4. `$ mkdir RPMS/i[3456]86 RPMS/noarch RPMS/athlon`
5. To override the default location of the RPM build tree, create or edit **.rpmmacros** in your home directory,
or use the following command.
`$ echo -e "%_topdir\t${PWD}" > ~/.rpmmacros`

 **Note:** this command overwrites the `.rpmmacros` file.

- To verify that the configuration was successful, check that the following command gives the correct path to the **SOURCES** directory.

```
$ rpm --eval %_sourcedir
```

For example: `/home/yourusername/src/rpm/SOURCES`

Obtaining the BigFix Remote Control Target Source RPM package

The source RPM package is obtained from the installation files. By default, this package will extract the install files for the target to the `IBM/Tivoli_Remote_Control` directory inside your home directory.


Installing the Source RPM package

Installing a source RPM package installs the files that are needed to build or rebuild the package into the RPM build tree.

Use the following command to install the package for the Target:

```
$ rpm -ivh ~/IBM/Tivoli_Remote_Control/RCTarget/ibm-trc-target-9.x.x.src.rpm
```

Where `9.x.x` is relevant to the version that you want to install. For example, `9.1.0`.

 **Note:** This command might generate warnings about users and groups that do not exist. These warnings are because your system does not have the user and groups that were used to build the original package. You can ignore these warnings.

Examples of the warning messages:-

Warning: user *user name* does not exist - using root

Warning: group build does not exist - using root

Warning: group trc_build does not exist - using root

To verify that this step was successful, check the `SPECS` and the `SOURCES` directories and make sure that the following files are there:

```
$ ls SPECS/ SOURCES/
```

```
SOURCES/: ibm-trc-target.tar
```

```
SPECS/: ibm-trc-target.spec
```

Customizing the SPEC file

To make sure that you can tell the customized package apart from the original package, you must customize the version number in the SPEC file. It is recommended that you use an identifier that is based on your organization's name. In this example "BFC Fiction Ltd" is used.

To customize the SPEC file, complete the following steps:

1. Edit the SPEC file.

You can use your favorite editor instead of vi.

```
$ vi SPECS/ibm-trc-target.spec
```

2. Change the line `version: ${_buildversion}` to `version: 5.1.2.bfc`

3. The release field must be updated as well.

This field can be used to track the version of your customized builds.

```
Change Release: %{_buildlevel} to Release: 1
```

Customising the default configuration file

Before the configuration file can be customised, it needs to be extracted from the tar archive into a temporary directory.

To extract the configuration file complete the following steps:

1. Create a temporary directory

```
$ mkdir SOURCES/ibm-trc-target
```

```
$ cd SOURCES/ibm-trc-target
```

2. Extract all the files from the tar archive

```
$ tar xvf ../ibm-trc-target.tar
```

3. Edit the configuration file with the customisations necessary for your environment.

```
$ vi ibmtrct.conf
```

For example: to enable the target for peer to peer failover set ALLOWP2P to Yes and ALLOWP2PFAILOVER to Yes. See

4. When the changes are complete the tar archive needs to be recreated so that the modifications are used by the RPM build process.

```
$ tar cvf ../ibm-trc-target.tar *
$ cd ../../
```

Building your customized BigFix Remote Control target RPM package

The following command will rebuild the RPM package using your customized configuration file.

```
$ rpmbuild -ba SPECS/ibm-trc-target.spec
```

The RPM package will be saved to `RPMS/i386/ibm-trc-target-5.1.2.bfc-1.i386.rpm`

You should now run the following command to install your customised target.

```
$ rpm -ivh RPMS/i386/ibm-trc-target-5.1.2.bfc-1.i386.rpm
```

Installing the target by using the SPB file

You can install the BigFix Remote Control target components on a Windows system and a Linux system by using the Software Package Block (SPB) installation method.

This method requires IBM® Tivoli® Provisioning Manager. The following files are required for the installation.


Windows systems


trc_target_win.spb

Linux systems

trc_target_linux.spb

These files can be extracted by using the additional setup utility. For more information about using the additional setup utility, see [Extract the installation files by using the additional setup utility \(on page 112\)](#)

 **Note:** If you are using Red Hat Linux 6.0 64-bit operating system, the following libraries along with their dependencies, need to be installed if they are not already installed, `glibc.i686`, `libgcc.i686`, `libXmu.i686`, `libXp.i686`, `libXtst.i686`.

 **Note:** Tivoli Common Agent (TCA) needs to be installed on the computers before the target can be installed using the SPB method.

Install the controller

The BigFix Remote Control controller can be installed locally on your system, to be used for connecting to a target directly if peer to peer mode is enabled.

BigFix Remote Control provides two ways to install the controller component. If you have access to the BigFix console, use the deployment Fixlet to deploy the controller. For more information, see [Deploy the BigFix Remote Control components](#) in the *BigFix Remote Control Console User's Guide*. Alternatively use the BigFix Remote Control controller installation files.

Installing the controller on a Windows system

The `trc_controller_setup.exe` file is required to install the controller component on a Windows system.


For more information about how to obtain the component installation files for a Windows system, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

1. Run the `trc_controller_setup.exe` file.
2. On the file download window, select **Run** or **Save**

Run

Select **Run** to start the installation wizard.

- a. Click **Next** at welcome screen.
- b. Accept the license agreement, click **Next**.
- c. Accept or change the location for the installation files, click **Next**.
- d. Click **Install**.
- e. Click **Finish**.

 **Note:** If the controller software is already installed on the system, modify, repair, or remove options are available.

Save

Select **Save** to save the `trc_controller_setup.exe` file to a selected location. Run the file to install the controller.

The controller is installed to the default location `\Program Files\IBM\Tivoli\Remote Control\Controller` or the location that is selected during the installation.

Installing the Linux controller

Use the `ibm-trc-controller-9.x.x.noarch.rpm` and `ibm-trc-controller-jre-9.x.x.i386.rpm` files to install the controller component in Linux. Where 9.x.x is relevant to the version that you want to install. For example, 9.1.0 For more information about how to obtain the Linux component installation files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

You can install the controller in two modes in Linux, a FIPS-compliant controller or a standard controller.

Type the relevant command for installing the controller. Where 9.x.x is relevant to the version that you want to install. For example, 9.1.2.


- For the standard controller type

```
#rpm -ivh ~/IBM/Tivoli_Remote_Control/RCTarget/ibm-trc-controller-9.x.x.noarch.rpm
```

- For a FIPS-compliant controller, install the standard controller and the FIPS-compliant JRE by running both commands.

```
#rpm -ivh ~/IBM/Tivoli_Remote_Control/RCTarget/ibm-trc-controller-9.x.x.noarch.rpm
```

```
#rpm -ivh ~/IBM/Tivoli_Remote_Control/RCTarget/ibm-trc-controller-jre-9.x.x.i386.rpm
```

 **Note:** Standard controller installations work with the `ibm-trc-controller-9.x.x.noarch.rpm` file, with an alternative JRE installed on the system. If the controller is to be FIPS-compliant, the `ibm-trc-controller-jre-9.x.x.i386.rpm` file must also be installed. The `ibm-trc-controller-jre-9.x.x.i386.rpm` file can also be installed even if the controller is not going to be run in FIPS mode.

You can start the controller from your applications list when it is installed.

Install the BigFix Remote Control Controller for macOS

The BigFix Remote Control Controller for macOS can be installed in multiple ways. You can use the `trc_controller.pkg` file to install the application. You can also install the controller by using a Fixlet in the BigFix console.

For information about how to obtain the BigFix Remote Control Controller for macOS component installation files see, [Obtain the installation files \(on page 22\)](#). Choose the appropriate method for obtaining the file.

Installing the BigFix Remote Control Controller for macOS from the BigFix console

You can use a Fixlet in the BigFix console to install the BigFix Remote Control Controller for macOS component. The deployment Fixlet is available in the Remote Control site in the Systems Lifecycle domain.

1. Within the **Systems Lifecycle** domain, expand **Remote Control configuration > Remote Control**.
2. Expand the **Deployment** node.
3. Select **macOS**.
4. Select **Deploy BigFix Remote Control Controller for macOS**.
5. In the **Task** pane, review the description and follow the instructions in the **Actions** box to start the task.
6. In the **Take Action** pane on the **Target** tab, select the relevant option for determining which computers to deploy the BigFix Remote Control Controller for macOS component on.
7. Click **OK**.

The summary screen shows the progress of the task and the status is set to **Complete** when it is finished.

Installing the BigFix Remote Control Controller for macOS

You can use the `trc_controller.pkg` file to install the BigFix Remote Control Controller for macOS.


You can obtain the `pkg` file from Passport Advantage or from the BigFix Remote Control server UI. For more information, see [Obtain the installation files \(on page 22\)](#). To install the controller, complete the following steps.

1. Double-click the `trc_controller.pkg` file.
2. Click **Continue**.
3. Click **Install** to install to the startup disk. If your system has multiple disks, you can select which disk to install the controller on. Click **Change Install Location** to select an installation disk.
4. If you are a user with admin authority, type in your password when prompted. Otherwise, type a valid admin ID and password. Click **Install Software**.
5. When the installation completes, click **Close**.

After you install the .pkg file, open the `Remote Control Controller.app` to start the target.

Installing the controller in other supported operating systems

If you are using a supported operating system other than Windows operating system, Linux, AIX, or Solaris (SPARC), extract the controller files by using the additional setup utility. Then, copy the required files to the system that you are running the controller on. You must run the additional setup utility on a Windows, Linux, AIX, or Solaris (SPARC) system. For more information about obtaining the additional setup utility files, see [Install the BigFix Remote Control components \(on page 22\)](#).

 **Note:** Ensure that you install a supported version of Java to run the controller on the other supported operating system. See [Controller requirements \(on page 16\)](#).

To install the controller, complete the following steps:

1. After you extract the installation files, go to the `RCController` directory.
2. Copy the file `trc_console.zip` to the system that you are running the controller on.
3. Extract the files from the `trc_console.zip` file.
4. Type the following command to run the controller

```
java -jar TRCConsole.jar
```

Installing a preconfigured controller component

You can configure the controller component by editing the `trc_controller.cfg` configuration file after the controller is installed. You can also apply custom configuration settings when you install the controller component. You can apply custom configuration settings when you install the controller component.

Preconfiguring the controller is useful for unattended installations. You can set your configuration file values in the configuration file and copy the file to the computers that you want to install the controller on. Your configuration settings are installed together with the controller. The configuration values are set in the `trc_controller.cfg` file. You can create the file and add your custom values or you can edit a default configuration file. If you do not apply any preconfiguration, the default configuration file is installed when you install the controller component.

The property values in the `trc_controller.cfg` are global and are the same for all users who run the controller. However, a user can create a local configuration. The values in the users' local configuration are used when they run the controller and override the global values. To enforce the global property value,

you can set a property to mandatory so that a user cannot edit the property in the **Configuration Window** in the controller UI. The mandatory global property overrides the local property.

To set a mandatory property, complete the following steps:

1. Open the `trc_controller.cfg` file.
2. Copy the property name and add `.mandatory = true` to the end.

For example, to make the **Enable Address History** property mandatory so that it cannot be edited in the **Configuration Window**.

```
enable.address.history=false
enable.address.history.mandatory=true
```


3. Save the file.

After you save the `trc_controller.cfg` file, install the controller.

Preconfigure the controller for a Windows operating system installation

1. Copy the `trc_controller.cfg` file to the same directory as the `trc_controller_setup.exe` or `trc_controller.msi` file.
2. Run the controller installation file.

The controller is installed with your configured settings.

 **Note:** Preconfiguring the controller is not supported for installation on a Linux operating system. If necessary, you can modify and rebuild the controller `.rpm` file from the source `.rpm` file.

Use the content of the default configuration file to create your custom configuration file and set your own values.

```
# Licensed Materials - Property of IBM
#
# 5725-C43
#
# Copyright International Business Machines Corp. 2011, 2014.
#All Rights Reserved
#
# US Government Users Restricted Rights - Use, duplication or disclosure
# restricted by GSA ADP Schedule Contract with IBM Corp.
```

```
fips.compliance=false
```

sp800131a.compliance=false

enable.address.history=true

enable.user.history=false

enable.domain.history=true

history.max.items=20

tool01.ToolName = Control Panel

tool01.ToolCommand = [SystemFolder]\\control.exe

tool01.ToolParameters =

tool01.ToolUser =

tool02.ToolName = Command Prompt

tool02.ToolCommand = [SystemFolder]\\cmd.exe

tool02.ToolParameters =

tool02.ToolUser =

tool03.ToolName = Administrator Command Prompt

tool03.ToolCommand = [SystemFolder]\\cmd.exe

tool03.ToolParameters =

tool03.ToolUser = admin

tool04.ToolName = Task Manager

tool04.ToolCommand = [SystemFolder]\\taskmgr.exe

tool04.ToolParameters =

tool04.ToolUser =

tool05.ToolName = Windows Explorer

tool05.ToolCommand = [WindowsFolder]\\explorer.exe

tool05.ToolParameters =

tool05.ToolUser =

tool06.ToolName=Terminal

tool06.ToolCommand=/usr/bin/gnome-terminal

tool06.ToolParameters =

tool06.ToolUser =

tool07.ToolName=Control Panel

tool07.ToolCommand=/usr/bin/gnome-control-center

tool07.ToolParameters =

tool07.ToolUser =

tool08.ToolName=

tool08.ToolCommand=

tool08.ToolParameters =

tool08.ToolUser =

tool09.ToolName=

tool09.ToolCommand=

tool09.ToolParameters =

tool09.ToolUser =

tool10.ToolName=

tool10.ToolCommand=

tool10.ToolParameters =

tool10.ToolUser =

Custom keys

example.KeySequenceName = Inject F1

example.KeySequenceValue = [F1]

#

For a list of supported key codes, please refer to the User's Guide

key01.KeySequenceName =

key01.KeySequenceValue =

key02.KeySequenceName =

key02.KeySequenceValue =

key03.KeySequenceName =

key03.KeySequenceValue =

Install the command-line tools

You can use the command-line tools to start a remote control session from the command-line, or run commands on a target system without target user interaction. The commands can be useful if you want to connect to a target without using the BigFix Remote Control Server interface or for using as part of a script to run multiple commands in an automated fashion. The command-line tools are only available to run on Windows operating systems and Linux operating systems.

BigFix Remote Control provides two ways to install the command-line tools. If you have access to the BigFix console, use the deployment fixlets to deploy the tools. For more information about deploying the components, see the *BigFix Remote Control Controller User's Guide*. Alternatively use the BigFix Remote Control controller installation files.

Installing the cli tools on a Windows system

The `trc_cli_setup.exe` file is required to install the controller component on a Windows system.

For more information about how to obtain the Windows component installation files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

1. Run the `trc_cli_setup.exe` file.
2. On the file download window, select **Run** or **Save**

Run

Select **Run** to start the installation.

- a. Click **Next** at the welcome screen.
- b. Accept the license agreement, click **Next**.
- c. Accept or change the location for the installation files, click **Next**.
- d. On the server address screen type in the information and click **Next**:

Server host name

Enter the IP address or server name of the BigFix Remote Control server.

Use secure connections (https)

Select https to use secure connections to contact the server.

Advanced settings

Click **Advanced settings** for more configuration settings.

Server port

Enter the port number that the server is listening on.

Server context

Enter a value for the server context. For example, `trc`.


Use a FIPS certified cryptographic provider

Select **Use a FIPS certified cryptographic provider** for installing FIPS-compliant tools.

Enable NIST SP800-131A compliance (Enables FIPS)

Select **Enable NIST SP800-131A compliance (Enables FIPS)** for installing NIST SP800-131A compliant tools.


- e. On the **Proxy settings** panel, if you are not using a proxy server click **Next**.
 - If you are using a Proxy, select **Use a proxy server or a Remote Control Gateway**. Type in the relevant information
 - i. Type in the IP address or host name for the proxy server.
 - ii. Type in the port that proxy server is listening on.
 - iii. Select **Use an HTTP proxy** or **Use a Remote Control Gateway**.
 - iv. Select **Proxy requires authentication** and enter the user ID and password for authenticating to the proxy server. The user ID and password are automatically encrypted when the target starts. For more information about the automatic passphrase encryption, see the *BigFix Remote Control Administrator's Guide*.

 **Note:** The CLI is unable to automatically encrypt the proxy credentials when the CLI is installed stand-alone, without the target and when the CLI is run by a standard user. If you use the CLI that is included in the target package, the proxy credentials are automatically encrypted by the target. You must restart the target after you edit the settings in the registry or configuration file. When you use the stand-alone CLI tools, you must run the CLI once from an **Administrator Command Prompt** in a Windows operating system or when logged in as root in Linux.
- v. Click **Next**.
- f. Accept the default port or type in a value, click **Next**
- g. Click **Install**.

h. Click **Finish**.

Save

Select **Save** to save the `trc_cli_setup.exe` file to a specific location.

 **Note:** Run this executable file to install the command-line software.

The following executable files are in the selected directory.

`wrc.exe`

Use this tool to start a remote control session with a target.


`wrcmdpccr.exe`

Use this tool to run a command on a target and see the output from the command on the computer that you issue the command from.


For more information about using the command line tools, see the *BigFix Remote Control Controller User's Guide*

Installing the CLI tools in Linux

You can install the CLI tools on a Linux computer by using the RPM file that is provided in the BigFix Remote Control installation files.

 **Note:** The target, CLI, gateway, and broker component installation packages depend on the 32-bit version of the following libraries. For all components, **glibc** and **libblkid**. Also, for the target component, **libgcc**, **libXmu**, **libXtst**, **libXp**, **libXi**, **libXScrnSaver**, and **libXinerama**. Therefore, you must ensure that the libraries are installed.

Use the `ibm-trc-cli-9.x.x.i386.rpm` file to install the CLI tools in Linux. Where 9.x.x is relevant to the version that you want to install. For example, 9.1.0 For more information about obtaining the Linux component installation files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

 **Note:** If the `ibm-trc-target` RPM file is installed, you do not need to install the `ibm-trc-cli` RPM file because the CLI commands are already included in the target. For more information about using the commands, see the *BigFix Remote Control Controller User's Guide*.

1. Type, the following command to install the command line software.

Where 9.x.x is relevant to the version that you want to install. For example, 9.1.0.

```
$ rpm -ivh ~/IBM/Tivoli_Remote_Control/RCTarget/ibm-trc-cli-9.x.x.i386.rpm
```

2. When the installation is complete, edit the `/etc/ibmtrct.conf` file and set your configuration.
 - Set the value of **ServerURL** to the host name or IP address of your BigFix Remote Control Server.
 - For FIPS-compliance set the value of **FIPSCompliance** to Yes.
 - For NIST SP800-131a compliance, set the value of `SP800131ACompliance` to yes.
3. Save the file.

For more information about using these commands, see the *BigFix Remote Control Controller User's Guide*.


Install gateway support in BigFix Remote Control

For targets, controllers, and server on different networks that cannot directly contact each other you can install and configure gateway support.

BigFix Remote Control provides two ways to install the gateway support. If you have access to the BigFix console, use the deployment fixlets to deploy gateway support. For more information, see the BigFix Remote Control Console User's Guide. Alternatively you can use the BigFix Remote Control gateway support installation files.

Installing Windows gateway support

The `trc_gateway_setup.exe` file is required to install gateway support in a Windows operating system. For more information about how to obtain the Windows gateway support files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

 **Note:** You can also install gateway support with no user interaction by running a silent installation. For more information about a silent installation, see [Installing the gateway support by running a silent installation \(on page 107\)](#).

To install gateway support, complete the following steps:

1. Run the `trc_gateway_setup.exe` file.
2. Click **Next** at the Welcome screen.
3. Accept or change the installation location and click **Next**.
4. Click **Install**.

5. Click **Finish** when the installation is complete.

When the gateway support is installed, you must configure it for your environment. For more information about configuring gateway support, see the *BigFix Remote Control Administrator's Guide*.

Installing the gateway support by running a silent installation

To install the gateway support on a Windows system by running a silent installation, complete the following steps:

1. Create a folder in your root drive called **IBMTRC**.
2. Copy **trc_gateway_setup.exe** file to **IBMTRC**.
3. Open a command prompt window and go to **IBMTRC**.
4. Type in the following command all in one line:

```
trc_gateway_setup.exe /s /v"/qn"
```

/s

Denotes a silent installation.

/v"

The string that is attached to /v contains the parameters for **msiexec.exe**, which is a piece of software that runs the actual installation.


/qn

Perform a silent installation with no progress window.

For more information about configuring gateway support, see the *BigFix Remote Control Administrator's Guide*.

Installing Linux gateway support

You can install gateway support on a Linux computer by using the RPM file that is provided in the BigFix Remote Control installation files.

 **Note:** The target, CLI, gateway, and broker component installation packages depend on the 32-bit version of the following libraries. For all components, **glibc** and **libblkid**. Also, for the target component,

libgcc, **libXmu**, **libXtst**, **libXp**, **libXi**, **libXScrnSaver**, and **libXinerama**. Therefore, you must ensure that the libraries are installed.

Use the `ibm-trc-gateway-9.x.x.i386.rpm` file to install gateway support in Linux. Where 9.x.x is the version that you want to install. For more information about obtaining the Linux gateway support files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

Type the following command at a command prompt to install the gateway support. Where 9.x.x is the version that you want to install. For example, 9.1.0.

```
$ rpm -ivh ibm-trc-gateway-9.x.x.i386.rpm
```

When the gateway support is installed, configure it for your environment. For more information about configuring gateway support, see the *BigFix Remote Control Administrator's Guide*.

Install broker support

Broker support must be installed on the computers that connect the controller to the target computer when the target computer is not directly accessible by the controller and the connection is made across the internet.

BigFix Remote Control provides two ways to install the broker support. If you have access to the BigFix console, use the deployment fixlets to deploy the broker support. For more information, see the *BigFix Remote Control Console User's Guide*. Alternatively use the BigFix Remote Control broker installation files.

Installing Windows broker support

The BigFix Remote Control broker installation files are executable files that can be used to install broker support on a Windows computer.

The `trc_broker_setup.exe` file is required to install broker support on a Windows system. For more information about how to obtain the Windows broker support files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

To install broker support on a Windows computer, complete the following steps.

1. Run the `trc_broker_setup.exe` file.
2. Click **Next** at the welcome screen.

3. Accept license terms and click **Next**.
4. Accept the default location or change the installation destination folder. Click **Next**.
Default location is `\Program Files\IBM\Tivoli\Remote Control\Broker`
5. Click **Install**.
6. Click **Finish**.

The following files are installed in the `[working dir]\Broker` directory, where `[working dir]` is determined by the version of Windows operating system that you are installing the broker support on.


For example, `\Documents and Settings\All Users\Application Data\IBM\Tivoli\Remote Control`.

- `trc_broker.properties`
- `TRCICB-computername-day.log` where `computername` is the computer name of the system that the broker is installed on and `day` is the day of the week that the broker is installed on.

You must check that the **BigFix Remote Control- Internet Connection Broker** service is registered and is started.

Installing Linux broker support

You can install broker support on a Linux computer by using the RPM file that is provided in the BigFix Remote Control installation files.

 **Note:** The target, CLI, gateway, and broker component installation packages depend on the 32-bit version of the following libraries. For all components, **glibc** and **libblkid**. Also, for the target component, **libgcc**, **libXmu**, **libXtst**, **libXp**, **libXi**, **libXScrnSaver**, and **libXinerama**. Therefore, you must ensure that the libraries are installed.

Use the `ibm-trc-broker-9.x.x.i386.rpm` file to install the broker support in Linux. Where `9.x.x` is the version that you want to install. For example, 9.1.0. For more information about obtaining the Linux component installation files, see [Install the BigFix Remote Control components \(on page 22\)](#). Choose the appropriate method for obtaining the file.

At a command prompt type, the following command to install the broker software. Where `9.x.x` is the version that you want to install. For example, 9.1.0.

```
rpm -ivh ibm-trc-broker-9.x.x.i386.rpm
```

The following files are installed in the `/opt/ibm/trc/broker` directory.


- `libcrypto.so.1.0.0`
- `libssl.so.1.0.0`
- `trc_icb`
- A license directory.

The `trc_broker.properties` file is installed in the `/etc` directory.

When the broker support is installed, configure the broker properties by editing the `trc_broker.properties` file.

Chapter 5. Utility for extracting the component installation files

BigFix Remote Control provides a utility that you can use to extract the installation files that are required for each component.

 **Note:** This utility can be run only on computers with a Windows, Linux, AIX, or Solaris SPARC operating system installed. For other supported operating systems, for example macOS or HP-UX, extract the installation files by running the utility on another computer. Copy the extracted files to the required computer.

Extract the data from the `BigFix_Rem_Cntrl_V914_Image_3.tar` file. Go to the `\Disk1\InstData\platform\VM` directory where *platform* is relevant to your operating system. The utility can be run only by using the `trc_additional_setup.exe` or `trc_additional_setup.bin` file. To extract the installation files for other supported operating systems, for example, macOS, run one of the `trc_additional_setup` files to extract the installation files, then copy the `.pkg` files to the macOS system.

Use the following files to run the additional setup utility:

Windows systems

`trc_additional_setup.exe`

AIX, Linux, Solaris systems

`trc_additional_setup.bin`

For more information about how to obtain the `BigFix_Rem_Cntrl_V914_Image_3.tar` file, see [Obtain the installation files \(on page 22\)](#).

You can extract the following component installation files.

- Server Installation media: Use the files to run a manual server installation. The `trc.war` file and instructions are extracted.
- Target Installation media:
 - Windows Packages (`.exe` and `.msi`)
 - Linux Package (`.rpm`)
 - macOS Package (`.pkg`)
- Controller installation media:
 - Windows Packages (`.exe` and `.msi`)
 - Linux Package (`.rpm`)

- macOS Package (.pkg)
- Command Line Interface installation media:
 - Windows Packages (.exe and .msi)
 - Linux Package (.rpm)
- Gateway installation media:
 - Windows Packages (.exe and .msi)
 - Linux Package (.rpm)
- Internet Connection Broker installation media:
 - Windows Packages (.exe and .msi)
 - Linux Package (.rpm)
- Server Installation media: Use the files to run a manual server installation. The `trc.war` file and instructions are extracted.
- Target Installation media: The target `.msi`, `.exe`, `.rpm`, and instructions files are extracted.
- Controller installation media.
- Command Line Interface Installation Media.
- Gateway Installation Media.
- Internet Connection Broker Installation Media.

Extract the installation files by using the additional setup utility

To run the additional setup utility, complete the following steps:

1. Run the `trc_additional_setup` file relevant to your operating system.
The file must be run from within the file structure that is extracted from the `BigFix_Rem_Cntrl_V914_Image_3.tar` file. For more information about which file to use, see [Utility for extracting the component installation files \(on page 111\)](#).
2. Select the language and click **OK**.
3. Accept the license agreement and click **Next**.
4. Clear the options that you do not want to extract the files for. Only the options you require must remain selected.
 - a. Server Installation media: to extract the files for installing the server.
 - b. Target Installation media: to extract the files for installing the target.
 - c. Controller Installation media: to extract the files for installing the controller.

- d. Command Line Interface Installation media: to extract the files for running the command line interface.
 - e. Gateway Installation media: to extract the files for installing gateway support.
 - f. Internet Connection Broker Installation media: to extract the files for installing broker support.
5. Click **Next**.
 6. Accept or change the installation folder. Click **Next**.
 7. On the summary screen, click **Install**.
 8. When complete, click **Done**.
 9. Go to the chosen installation folder.

The installation files are in the following directories:

- **RCServer** - server installation file, `trc.war`.
- **RCTarget** - target installation files.
- **RCController** - controller installation files.
- **RCCLI** - command line tools installation files.
- **RCGateway** - gateway installation files.
- **RCBroker** - broker installation files.

Chapter 6. Enable secure target registration


To prevent unauthorized targets from registering with the BigFix Remote Control server, you can enable the secure registration feature and use tokens to authenticate the target.

The secure registration feature is enabled by default on a new BigFix Remote Control server installation when you use the installer program. After you install the server, create a registration token on the server and use it when you install the target. For more information about the secure registration feature and how to create a token, see Secure target registrationthe **Secure target registration** chapter in the *BigFix Remote Control Administrator's Guide*

Enable secure target authentication in the server

The BigFix Remote Control Server provides an installation option to enable secure registration of targets.

When the feature is enabled, the server verifies that a secure registration token that is sent by the target matches an existing token on the server. If the token is valid, the target is registered in the server and receives an endpoint token from the server. The target sends the endpoint token to the server each time it contacts the server.

 **Note:** If you have existing targets in the database and you enable the secure registration feature, the existing targets cannot successfully contact the server because they do not have an endpoint token. Therefore, you must create or use a valid a secure registration token and reinstall the existing targets with the token so that they can continue to contact the server.

Enabling secure registration when you run the server installer program

You can enable the secure target registration feature when you install the server by using the installer program. The feature is enabled by default on a new server installation.

To enable the secure registration feature, complete the following steps:

1. Follow the installation steps in [Installing by using the server installer \(on page 32\)](#).
2. On the **Web server parameters** window, ensure that **Force targets to use https** is selected.
3. Select **Use secure registration tokens to register targets**.
4. Complete the installation.

After you install the server and enable the secure target registration feature, create registration tokens. For more information about creating registration tokens, see *Creating a secure registration token* in the *BigFix Remote Control Administrator's Guide*.

Enabling secure target registration after you install the server

You can enable the secure target registration feature after you install the server by editing properties in the `trc.properties` file.

To enable the secure registration feature after you install the server, complete the following steps.

1. In the server UI select **Admin > Edit properties file**.
2. Select `trc.properties` from the list.
3. Set `rc.enforce.secure.registration` to `true`.

Ensure that the `enforce.secure.endpoint.callhome` and `enforce.secure.endpoint.upload` properties are also set to `true`.

4. Click **Submit**.
5. Click **Admin > Reset Application**.

You can also manually edit the properties files and set the property to `true`. Restart the server after you edit the file. The properties files are in the following directories:

Windows systems

`[installdir]\wlp\usr\servers\trcserver\apps\TRCAPP.ear\trc.war\WEB-INF\classes`

Where *installdir* is the directory that the BigFix Remote Control Server is installed. For example,

```
C:\Program Files\IBM\Tivoli\TRC\server\wlp\usr\servers\trcserver
\apps\TRCAPP.ear\trc.war\WEB-INF\classes
```

Linux systems

`[installdir]/wlp/usr/servers/trcserver/apps/TRCAPP.ear/trc.war/WEB-INF/classes`

Where *installdir* is the directory that the BigFix Remote Control Server is installed. For example,

```
/opt/IBM/Tivoli/TRC/server/wlp/usr/servers/trcserver/apps/TRCAPP.ear
/trc.war/WEB-INF/classes
```

Add a token for secure target registration

The BigFix Remote Control Target provides an installation option to add a secure registration token. You can also add the token by running a Fixlet in the BigFix console.

The token is used to prevent unauthorized targets from registering with the BigFix Remote Control server. Create a token on the server and use it when you install the target. The secure registration feature on the server must also be enabled.

The target sends the secure registration token to the server the first time it contacts the server. The server verifies that the token matches an existing token on the server. If the token is valid, the target is registered in the server and receives an endpoint token from the server.

Note:

The target includes the token in its callhome to the server only when it uses a secure connection to the server. The server URL that it uses to connect to the server must start with HTTPS.

The token is used to restrict new target registrations, or restrict updates to existing target details when you reinstall a target. After the target registers, the server sends a new token to the target to replace the token that was used when it registered. The target uses the new token to authenticate to the server each time it contacts the server. The feature is controlled by the **rc.enforce.secure.registration** property in the `trc.properties` file.

true

Secure target registration is enabled. Secure tokens are used to authenticate a target when it contacts the server. This value is the default value.

false

Secure target registration is disabled.

The secure registration feature is enabled by default on a new server installation when you are using the installer program. For an upgrade, you can enable it during the server installation, or after installation by editing the **rc.enforce.secure.registration** in the `trc.properties` file.

New installations

1. Install the server
2. Create a registration token
3. Install the targets along with the registration token

Upgrades

1. Upgrade the server
2. Create a registration token
3. Upgrade the targets along with the registration token
- 4.

After you install the server, you can create a registration token. For more information about creating the token, see

Add the secure registration token when you install the target on a Windows system

On a Windows system, you can add a secure registration token in multiple ways:

- Add the token by using the target installer program.
- Add the token by running the target installation from the command line.
- Modify the target after installation.

Running the target installer with a secure registration token

When you install the target component, use the BigFix Remote Control Target installer to provide the target with a secure registration token. The target uses the token to authenticate to the server when it contacts the server for the first time.

To run the target installer with a token, complete the following steps:

1. Follow the installation steps in [Installing the Windows target \(on page 57\)](#).
2. On the **Server Address** window, for secure target registration, enter or paste the token in the **Secure registration token** field.
Ensure that **Use secure connections (https)** is also selected. For more information about secure target registration, see [Add a token for secure target registration \(on page 115\)](#).
3. Complete the installation.

Running a target silent installation with a secure registration token

Install the target along with a secure registration token when you run a new BigFix Remote Control target silent installation.

For more information about running a target custom installation, see [Run a target custom installation \(on page 84\)](#) the *BigFix Remote Control Installation Guide*.

To install the target component and the token, run the following command on one line.

```
trc_target_setup.exe /s /v"/qn REGISTRATIONTOKEN=xxxxxxxxxxx  
TRC_SERVER_HOSTNAME=yyyyyyyyyyyyyyy"
```

Replace xxxxxxxxxxxx with the token and yyyyyyyyyyyyyy with the host name of your BigFix Remote Control server.

For more information about running a silent installation when you upgrade the target, see [Upgrading the target with a secure registration token \(on page 119\)](#).

Adding the secure registration token after you install the target

If you install the target component and do not install the secure registration token, you can modify the target and add the token.


Select the method for adding the token.

To add the token by running the installer program, complete the following steps:

1. Go to the **Control Panel**. For example, **Start > Control Panel > Programs > Programs and Features**.
2. Right-click **BigFix Remote Control-Target**.
3. Select **Change**.
4. On the **Program Maintenance** window, select **Modify**.
5. Click **Next** until the **Server Address** window is displayed.
6. Enter or paste the token in the **Secure registration token** field. Ensure that **Use secure connections (https)** is also selected.
7. Click **Install**.
8. Click **Finish**.

To add the token by editing the target registry, complete the following steps:

1. Edit the target registry and go to `HKEY_LOCAL_MACHINE\SOFTWARE\IBM\Tivoli\Remote Control\Target`

 **Note:** On a 64-bit system, all the 32-bit registry keys are under the **Wow6432Node** key. For example, `HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\IBM\Tivoli Remote Control\Target`

2. Right-click **RegistrationToken**.
3. Click **Modify**.
4. Enter or paste the token.
5. Restart the target.

Upgrading the target with a secure registration token

Upgrade the BigFix Remote Control target with a secure registration token.

The upgrade process requires two steps. You must upgrade the target first, then run an installation with the token.

- To use the installer to upgrade the target with a token, complete the following steps:
 1. Run the `trc_target_setup.exe` file.
 2. Select **Yes** for an automatic upgrade.
 3. Click **Next**.
If a **Files in Use** window is displayed, click **OK**.
 4. Click **Finish**.
 5. To add the token, complete the steps in, [Adding the secure registration token after you install the target \(on page 118\)](#).
- To run a silent installation to upgrade the target with a token, complete the following steps.
 1. At a command prompt type `trc_target_setup.exe /s /v"/qn"` to upgrade the target.
 2. To add the token run `trc_target_setup.exe /s /v"/qn REGISTRATIONTOKEN=xxxxxx REINSTALL=ALL"`
Where `xxxxxx` is replaced by the token that you saved when you created a token.

Add the registration token when you install a target on a Linux system

On a Linux system, you can add a registration token for secure target authentication by editing the `/etc/ibmtrct.conf` file after you install the target.

To add a secure registration token to a Linux target, complete the following steps after you install the target. For more information about installing the target on a Linux system, see [Installing the Linux target \(on page 81\)](#).

1. Edit the `/etc/ibmtrct.conf` file.
2. Add the registration token property and set it to the value of your registration token. Set **RegistrationToken** = `xxxxxxxxxxxxxxx`, where `xxxxxxxxxxxxxxx` is replaced with your token data. For example, `6386e21f-4316-460b-b339-deb3d132f3c7`
3. Save the file.
4. Restart the target service. For more information, see [Starting, stopping, or restarting the Linux components \(on page 127\)](#).

Chapter 7. Install a driver to support smart card authentication in the target


The BigFix Remote Control Target provides an installation option to install a virtual smart card reader driver. You can also install the driver by running a fixlet in the BigFix console.

The device driver for the IBM virtual smart card reader is required to enable the use of smart cards for remote authentication, or to perform an action on the target computer.

During a remote control session, the target creates a virtual card reader. The controller user selects a physical card reader on their system to connect it to the virtual card reader so that the target system can access the smart card. During the session, when Windows makes a request to the virtual card reader, the target redirects the request to the physical card reader on the controller system.

For more information about using the smart card feature during a session see, *Connecting to a smart card reader during a session* the *BigFix Remote Control Controller User's Guide*.

The device driver for the IBM virtual smart card reader is supported only in Windows 7 or later and Windows Server 2008 R2 or later.

 **Note:** Installation of the driver on Windows 7 or Windows server 2008 R2 might require the following updates to be installed on the target.

KB2921916

Microsoft hotfix to resolve the "Untrusted publisher" dialog box appears when you install a driver in Windows 7 or Windows Server 2008 R2 issue.

KB3033929

Security Update for Windows 7 for x64-based Systems.

Installing the virtual smart card reader driver by using the installer

Use the BigFix Remote Control Target installer to install the device driver for the IBM virtual smart card reader when you install the target component. You can also use the installer to install the driver on a system that has the target component already installed.

For more information about adding the driver after you install the target, see [Adding or removing the virtual smart card reader driver by using the installer \(on page 122\)](#).

To install the target software and the device driver for the IBM virtual smart card reader, complete the following steps:

1. Follow the installation steps in [Installing the Windows target \(on page 57\)](#)
2. On the **Additional features** window, select **Install device driver for Virtual Smart Card Reader**.

After you install the driver, you must install a certificate so that the target can automatically enable the driver when smart card authentication is requested. For more information about installing the certificate by running a Fixlet, see [Installing the certificates by running a Fixlet \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*. You can also download the certificates and install them manually. For more information, see [Downloading the certificates for the IBM virtual smart card reader \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*.

Adding or removing the virtual smart card reader driver by using the installer

After you install the target component, you can add or remove the device driver for the IBM virtual smart card reader by using the installer.

If you install the target component and do not install the device driver, you can modify the target and add the driver. To add the driver, complete the following steps:

1. Go to the **Control Panel**. For example, **Start > Control Panel > Programs > Programs and Features**.
2. Right-click **BigFix Remote Control-Target**.
3. Select **Change**.
4. On the **Program Maintenance** window, select **Modify**.
5. Click **Next** until the **Additional features** window is displayed.
6. Select **Install device driver for Virtual Smart Card Reader**. Click **Next**.
7. Click **Install**.
8. Click **Finish**.

The target can automatically enable the driver when smart card authentication is requested during a remote control session. Use the same procedure to remove the driver. In step [6 \(on page 122\)](#), clear **Install device driver for Virtual Smart Card Reader**.

After you install the driver, you must install a certificate so that the target can automatically enable the driver when smart card authentication is requested. For more information about installing the certificate by running a Fixlet, see [Installing the certificates by running a Fixlet \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*. You can also download the certificates and install them manually. For

more information, see [Downloading the certificates for the IBM virtual smart card reader \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*.

Installing the virtual smart card reader driver by running a silent installation

Install the device driver for the IBM virtual smart card reader when you run an BigFix Remote Control target silent installation.

You can install the driver when you run a silent installation on a computer that does not have the target component. You can also add or remove the driver from an installed target. For more information about running a target custom installation, see [Run a target custom installation \(on page 84\)](#).

- To install the target component and the device driver for the IBM virtual smart card reader, run the following command.

```
trc_target_setup.exe /s /v"/qn VSC=1"
```

- To add the driver to an installed target, run the following command.

```
trc_target_setup.exe /s /v"/qn ADDLOCAL=vsc REINSTALL=service"
```

- To remove the driver from an installed target, run the following command.

```
trc_target_setup.exe /s /v"/qn REMOVE=vsc REINSTALL=service"
```

After you install the driver, you must install a certificate so that the target can automatically enable the driver when smart card authentication is requested. For more information about installing the certificate by running a Fixlet, see [Installing the certificates by running a Fixlet \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*. You can also download the certificates and install them manually. For more information, see [Downloading the certificates for the IBM virtual smart card reader \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*.

Installing the virtual smart card reader driver when you upgrade the target

Install the device driver for the IBM virtual smart card reader when you upgrade the BigFix Remote Control target.

- To install the driver when you upgrade the target by using the installer, complete the following steps:

1. Run the `trc_target_setup.exe` file.
 2. Select **Yes** for an automatic upgrade.
 3. Click **Next**.
If a **Files in Use** window is displayed, click **OK**.
 4. Click **Finish**.
 5. To install the driver, complete the steps in, [Adding or removing the virtual smart card reader driver by using the installer \(on page 122\)](#).
- To install the driver when you upgrade by running a silent installation, complete the following steps.
 1. At a command prompt type `trc_target_setup.exe /s /v"/qn"` to upgrade the target.
 2. To add the driver run `trc_target_setup.exe /s /v"/qn ADDLOCAL=vsc REINSTALL=service"`.

After you install the driver, you must install a certificate so that the target can automatically enable the driver when smart card authentication is requested. For more information about installing the certificate by running a Fixlet, see [Installing the certificates by running a Fixlet \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*. You can also download the certificates and install them manually. For more information, see [Downloading the certificates for the IBM virtual smart card reader \(on page 125\)](#) the *BigFix Remote Control Console User's Guide*.


Installing the virtual smart card reader driver and certificates by running a Fixlet

Install the device driver for the IBM virtual smart card reader together with the certificates by running a Fixlet in the BigFix console.

You can install the driver and certificates by running a Fixlet after you install the target. To install the driver and certificates, complete the following steps:

1. In the **Remote Control** site, click the **Deployment** node.
2. Select the **Install BigFix Remote Control Virtual Smart Card Reader Driver version 9.1.4.0500 and certificates** task.
3. Review the information in the **Description** tab.
4. Follow the instructions in the **Actions** field to install the driver.

The device driver and certificates that are required for smart card authentication are installed. During a remote control session, when the controller user selects a physical card reader on their system, the target can now create a virtual card reader.

 **Note:** If an error is reported when you run the Fixlet, use the `VSCDriverInstall.log` file in the target installation directory for debugging purposes.


Installing the certificates by running a Fixlet

Use a Fixlet to install the certificates that are required by the device driver for the IBM virtual smart card reader.

You can install the certificates together with the driver by running a Fixlet. However, if the results of the **BigFix Remote Control - Virtual Smart Card Reader Driver Status** analysis show that the device driver is installed on your computer, but there are no certificates, you can install the certificates by running a Fixlet. To install the certificates, complete the following steps:

1. In the **Remote Control** site, click the **Deployment** node.
2. Select the **Install BigFix Remote Control Certificates for the Virtual Smart Card Reader Driver version 9.1.4.0500** task.
3. Review the information in the **Description** tab.
4. Follow the instructions in the **Actions** field to install the driver.

The certificates that are required for smart card authentication are installed. For more information about the **BigFix Remote Control - Virtual Smart Card Reader Driver Status** analysis, see Determining whether smart card support is enabled.

 **Note:** If an error is reported when you run the Fixlet, use the `VSCCertsInstall.log` file in the target installation directory for debugging purposes.

Downloading the certificates for the IBM virtual smart card reader

You can download the certificates that are required by the device driver for the IBM virtual smart card reader and install them manually. For example, by using Active Directory Group Policy.

You can download the certificates in multiple ways. Choose the method for downloading the certificates.

- Download the files from the Remote Control site in the BigFix console:
 1. Click the **Deployment** node and select the **Install BigFix Remote Control Virtual Smart Card Reader Driver version 9.1.4.0500 and certificates** task.
 2. Select the **Description** tab.
 3. Follow the instructions in the **Description** field to download the certificates.
 4. Save the `vsc_certs_0502.zip` file.
 5. Extract the certificate files from the `.zip` file.
- Extract the certificate files from the installation media:
 1. Access the BigFix Remote Control V9.x.x Image 1 in Passport Advantage. For more information about the image file, see [Obtain the installation files \(on page 22\)](#).
 2. Download the `BigFix_Rem_Cntrl_V9xx_Image_1.zip` file, where 9xx is relevant to the version that is installed.
 3. Extract the certificate files from the `\Windows` directory of the `.zip` file.

When you install the certificates, you must install the `ibm_corporation.crt` file to the Trusted Publishers store. Install the `TrustedRoot.crt` and `verisign-universal.cer` files to the Trusted Root Certificate Authorities store.

Chapter 8. Manage the component services

After you install the BigFix Remote Control components, if you change their configuration, you can stop, start, or restart the component services.

Follow the steps in the section that is relevant to your operating system.

Starting, stopping, or restarting the Windows components

You can start, stop, or restart the BigFix Remote Control Windows components from within the Control Panel.

To manage the BigFix Remote Control Windows components, complete the following steps.

1. In **Control Panel** select **Administrative tools > Services**.
2. Highlight the relevant service.

Server service

BigFix Remote Control- Server

Target service

BigFix Remote Control- Target

Gateway service

BigFix Remote Control- Gateway

Broker service

BigFix Remote Control- Internet Connection Broker

3. Choose the appropriate method for selecting an action for the service.
You can right-click and select **start**, **stop**, or **restart** or select **Start**, **Stop**, or **Restart** from the list on the left.

Starting, stopping, or restarting the Linux components

You can start, stop, or restart the BigFix Remote Control Linux components from within the Control Panel.

Depending on the version of Linux you are using, use one of the following commands to manage the components.

- `/sbin/service component action`
- `/etc/init.d/component action`

Where *component* is the component service that you want to manage and *action* is start, stop, or restart.

Server

For example, to start the server service.

- `/sbin/service trcserver start`
- `/etc/init.d/trcserver start`

Target

For example, to stop the target service.

- `/sbin/service ibmtrct stop`
- `/etc/init.d/ibmtrct stop`

Gateway

For example, to restart the gateway service.

- `/sbin/service ibmtrcgw restart`
- `/etc/init.d/ibmtrcgw restart`

Broker

For example, to restart the broker service.

- `/sbin/service ibmtrcicb restart`
- `/etc/init.d/ibmtrcicb restart`

Chapter 9. Enabling email

To use the email function, you must install and set up an email server. For example, for a forgotten password, to export and email a report, or to request access to certain targets.

To enable the email function, complete the following steps:

1. Log on to BigFix Remote Control server with a valid admin ID and password.
2. Click **Admin > Edit properties files**.
3. Select **trc.properties**.
4. Edit the following variables

email.enabled

Set to true to enable email.

SMTP.server

Set to the address of your mail server.

SMTP.authentication

Set to true or false, Set to true to authenticate with the SMTP ID and password.

SMTP.userid

User ID for the SMTP server.

SMTP.password

Password for the SMTP server.

5. Click **Submit**.

The email function is enabled.

Chapter 10. Configure LDAP

BigFix Remote Control provides Lightweight Directory Access Protocol Version 3 support. You can use LDAP to enable authentication and integration of users and their associated group membership into the BigFix Remote Control database.

All configuration information that is required for LDAP authentication is in the `ldap.properties` file. Before you configure, some prerequisite information must be obtained. This information simplifies the configuration process.

- A user name and password to be used by BigFix Remote Control to establish a connection with the Active Directory server. This user name must have the authority necessary to read all the required information from the directory tree.
- The fully qualified server host name or IP address of the Active Directory server to be used with BigFix Remote Control.
- In an Enterprise scenario, a secondary backup LDAP server would also be configured in BigFix Remote Control.

Setting up LDAP synchronization

To enable LDAP authentication, synchronization with the LDAP server must also be enabled. Edit values in the `common.properties` file and the `ldap.properties` file to enable synchronization.

To perform the basic configuration for LDAP authentication, complete the following steps:


1. Click **Admin > Edit properties file**.
2. Ensuring that you are editing the `common.properties` file, edit the following properties

authentication.LDAP

To enable or disable LDAP authentication.

True

LDAP user authentication is enabled.

 **Note:** Each time the synchronization with Active Directory takes place the users and user groups are deleted from the BigFix Remote Control database and then imported from Active Directory. Therefore, if LDAP

is enabled, new users and new user groups must be created in Active Directory and not in BigFix Remote Control.

False

LDAP user authentication is not enabled. Users are authenticated against the BigFix Remote Control database.

```
authentication.LDAP=true
```

authentication.LDAP.config

Defines the file that contains the LDAP configuration properties.

```
authentication.LDAP.config=ldap.properties
```

sync.ldap

Synchronize the users and groups from Active Directory with the BigFix Remote Control database. Takes the values true, to synchronize or false, for no synchronization.


True

The LDAP server is synchronized with the BigFix Remote Control database to reflect any changes that are made in LDAP.

False


No synchronization takes place. If synchronization is disabled, you must manually import the users into the BigFix Remote Control database.

Otherwise, they cannot log on to the BigFix Remote Control server. The users must exist in the BigFix Remote Control database so that they can be associated with the relevant permissions that are required to establish remote control sessions.

 **Note:** The synchronization is performed by running a scheduled task. The task pulls the LDAP information from the LDAP server and updates the database with any changes that are made to the user or group information. Within the `trc.properties` file, two attributes define the time interval that the scheduler uses to check for scheduled tasks.

scheduled.interval

The frequency that the server must check for scheduled tasks. The number of units of time between each checking period. Default is 60.

 **Note:** If you change this value, restart the server service for the new value to take effect.

scheduled.interval.period

The unit of time to be used along with the scheduled interval to specify how often the server must check for scheduled tasks. Default is minutes.

The **scheduled.interval** attribute is set to 60 as default and the **scheduled.interval.period** set to minutes, that is, the server checks for and runs any scheduled tasks every 60 minutes. To accurately reflect any changes to the users or groups, set the **scheduled.interval** attribute to a lower value so that the synchronization can occur more frequently.

3. Click **Submit**.

Verifying connection information

Use parameters to define how BigFix Remote Control connects to the LDAP server. The connection is used to query the LDAP server for the user and group information that is imported into BigFix Remote Control.

Any changes to the `ldap.properties` file do not take effect until you select **Admin,Reset Application**. To avoid multiple restarts or an extended outage use an LDAP browser and the **LDAP Configuration Utility** as an aid to the entire configuration process.

To verify the connection information by using an LDAP browser, define an LDAP server profile by entering the fully qualified host name and credential information. When you open an LDAP browser for the first time, provide details for a new profile.

The profile can include the following information.

Host

Host name or FQDN of the preferred LDAP Server.

Port

Port that is used to communicate with the directory. Typically, port 389 but if your environment contains child domains, port 3268 must be used instead. Port 3268 points to the Global catalog that includes the child domains.

Base DN

The root point to bind to the server. For example,

```
DC=mydomain,DC=mycompany,DC=com.
```


After the information is entered, the LDAP Browser displays attribute names and values available at the root of the Active Directory tree.


When a connection is established, use the same information that is used in the LDAP browser to set the parameters in the `ldap.properties` file.

- Click **Admin > Edit properties files**
- Select **ldap.properties** from the list
- When modifications are complete, click **Submit**

The application must be reset for the changes to take effect. Click **Admin > Reset Application** or restart the server service.

The properties file can also be edited manually by locating it on the BigFix Remote Control Server. The file is in the `[installdir]wlp\usr\servers\trcserver\apps\TRCAPP.ear\trc.war\WEB-INF\classes` directory, where `installdir` is the directory that the BigFix Remote Control Server is installed in. For example, `C:\Program Files\IBM\Tivoli\TRC\server\wlp\usr\servers\trcserver\apps\TRCAPP.ear\trc.war\WEB-INF\classes`


 **Note:** BigFix Remote Control is provided with a default `ldap.properties` file and many of the extended configuration options are commented out. To enable the options, the file must be edited manually.

 **Note:** The BigFix Remote Control Server is capable of managing one Global catalog only. This means that domain controllers of different domains cannot be managed by the same BigFix Remote Control Server.

Users belonging to a domain which is not included in the forest specified in the server configuration cannot be added to the users of the same BigFix Remote Control Server.

Configuring connection credentials

Use the following properties to set valid credentials for connecting to the LDAP server.

 **Note:** Check that a successful connection to the LDAP browser can be established by using these credentials to verify that they are valid.

1. Edit the `ldap.properties` file.

2. Configure the following properties.

ldap.connectionName

The user name that is used to authenticate to a read-only LDAP connection.

If left not set, an anonymous connection is attempted. For example,

`administrator@mydomain.mycompany.com`.

ldap.connectionPassword

The password that is used to establish a read-only LDAP connection. The password can be entered here in plain text or it can be encrypted. Use the LDAP wizard to encrypt your password. For more information, see Configure LDAP properties by using the LDAP wizard.

ldap.connectionPasswordEncrypted

True

The LDAP password is encrypted.

False

The LDAP password is not encrypted and entered as plain text.

Use the following method to generate the encrypted password. In a Windows system.

a. Open a command prompt window and type

```
cd [installdir]\wlp\usr\servers\trcserver\apps\TRCAPP.ear\trc.war\
WEB-INF\lib
```

where *installdir* is the BigFix Remote Control server installation directory For example,

```
cd \Program Files\IBM\Tivoli\TRC\server\wlp\usr\servers\trcserver\
apps\TRCAPP.ear\trc.war\WEB-INF\lib
```


b. Type the following command

```
java -cp ./trc.jar com.ibm.uk.greenock.authentication.Encrypt <password>
```

Where *password* is the LDAP password to be encrypted.

For example,

```
java -cp ./trc.jar com.ibm.uk.greenock.authentication.Encrypt myPassw0rd
```

 **Note:** This command is all on one line with a space between **jar** and **com**.

c. The following output from the command can be displayed.

Encrypted Password : [encrypted password]

Decrypted Password : [text version of password]

For example,

Encrypted Password: 10jydEBI67atSSbrAA=

Decrypted Password: myPassw0rd

Edit the `ldap.properties` file and set the `ldap.connectionPassword` property to the encrypted password value. The decrypted password is shown to verify that the encryption is valid.

In a UNIX or Linux system.

- a. Open a terminal window and type

```
[installdir]/wlp/usr/servers/trcserver/apps/TRCAPP.ear/trc.war/  
WEB-INF/lib
```

where `installdir` is the BigFix Remote Control server installation directory

- b. Type the following command

```
java -cp ./trc.jar com.ibm.uk.greenock.authentication.Encrypt <password>
```

- c. The output from the command is the following

Encrypted Password : [encrypted password]

Decrypted Password : [text version of password]

ldap.connectionURL

The directory URL used to establish an LDAP connection. Type in the URL of your LDAP server.

```
ldap://myldapservice.mydomain.mycompany.com
```

Setting connection security

The following properties define the level of security to be used on the connection to the LDAP server. Set the following parameter to `simple` so that the BigFix Remote Control server can communicate with most Active Directory servers.

ldap.security_authentication

Specifies the security level to use. Value can be set to one of the following strings: none, simple, strong. If this property is unspecified, the behavior is determined by the service provider.

```
ldap.security_authentication=simple
```

While most LDAP servers support simple plain text login, some Active Directory administrators require a secure connection. BigFix Remote Control supports two types of secure connections to an Active Directory server, **SASL** (Digest-MD5) or **SSL**. If you cannot connect to the Active Directory server and see the following error in the `trc.log`:

```
LDAP Authentication.exception[LDAP: error code 8 - 00002028: LdapErr: DSID-0C09018A,
comment: The server requires binds to turn on integrity checking if SSL\TLS are not
already active on the connection, data 0, vece ]
```

BigFix Remote Control needs to be configured for either SASL or SSL connections.

SASL (Simple Authentication and Security Layer)

The following parameters relate to using SASL to secure the connection to the LDAP server. If you are not using SASL, the parameters must not be edited. Comment out the parameters. The following values are used to configure BigFix Remote Control to connect to Active Directory that uses SASL in a test environment. Consult your organizations active directory support team to acquire the correct values for your company.

ldap.security_authentication

Specifies the security level to use. If this property is unspecified, the behavior is determined by the service provider. If you are using SSL, the value is set to simple. If you are using SASL, the value is set to the SASL mechanism DIGEST-MD5.

```
ldap.security_authentication= DIGEST-MD5
```

ldap.connectionRealm

The Realm name where the user ID and password resides.

```
ldap.connectionRealm= mydomain.mycompany.com
```

ldap.connectionQop

This value can be one of:

- auth = Authentication only
- auth-int = Authentication and integrity checking by using signatures
- auth-conf = (SASL only) Authentication, integrity and confidentiality checking by using signatures and encryption.

```
ldap.connectionQop= auth-conf
```


ldap.connectionMaxbuf

Number that indicates the size of the largest buffer the server is able to receive when you use *auth-int* or *auth-conf*. The default is 65536.

```
ldap.connectionMaxbuf= 16384
```

ldap.connectionStrength

Connection strength can be one of: low, medium, high.

```
ldap.connectionStrength= high
```

SSL (Secure Socket Layer)

The following parameters define the use of SSL to connect to the Active Directory server. To use SSL, you must install a Root CA public key certificate keystore on the BigFix Remote Control Server. If SSL is not used, the parameters can be commented out in the `ldap.properties` file.

ldap.security_protocol

Specifies the security protocol to use. The value is a string that is determined by the service provider. For example, `ssl`. If this property is unspecified, the behavior is determined by the service provider.

```
ldap.security_protocol =ssl
```

ldap.ssl_keyStore

Enter the location of the keystore file.

```
ldap.ssl_keyStore=PathOfKeyStoreFile
```

ldap.ssl_keyStorePassword

Enter the location of the keystore password.

```
ldap.ssl_keyStorePassword=KeystorePassword
```

Setting user authentication properties

Authenticating the user

Use the following properties to define how the user is authenticated when they attempt to log on to the BigFix Remote Control server. To configure the following sections use the LDAP browser as described for each parameter, to derive the correct settings.

ldap.digest

Digest algorithm that is used by LDAP. Values are SHA, MD2, or MD5 only. The default is cleartext. If the LDAP servers returns a password, BigFix Remote Control uses the Digest algorithm to encrypt the user input password and compare it with the password it receives from the LDAP server. If no password is returned from the LDAP server, BigFix Remote Control uses the user name and password that is provided by the end user to authenticate with LDAP.

```
ldap.digest=SHA
```

ldap.userid

ldap.userid is the LDAP attribute that contains the user ID that is mapped to the **userid** field in the BigFix Remote Control database. The **userPrincipalPattern** property then needs to know whether the *@domainname*, UPN suffix, is added for Active Directory authentication.

sAMAccountName

sAMAccount must be used so that the user ID only portion of the logon, without the UPN Suffix, is used.

userPrincipalName

userPrincipalName must be used to force all logons to use the full User Principal Name.

 **Note:** It is recommended to set **ldap.userid** to this value to ensures that it does not contain any invalid characters. For example, an apostrophe.

The **ldap.userid** relates to other configuration values in the `ldap.properties` file.

For example, if the `ldap.userid` is set to `userPrincipalName`, the user must log on to BigFix Remote Control with their full ID. For example, `awilson@example.com`.

- The **ldap.userSearch** variable would be `(userPrincipalName={0})`.
- The **ldap.principalPattern** would be `{0}`.

If the `ldap.userid` is set to use `sAMAccountName`, the user must log on to BigFix Remote Control with just the user ID part of their ID. For example, `awilson`. The following parameters must be set so that the fully qualified name is appended.

For example

- The **ldap.userSearch** variable would be
(`userPrincipalName={0}@mydomain.mycompany.com`)

For a user `awilson@example.com`, the **ldap.userSearch** variable would be
(`userPrincipalName={0}`)
- The **ldap.principalPattern** would be `{0}@mydomain.mycompany.com`.

For a user `awilson@example.com`, the **ldap.principalPattern** would be
`{0}@example.com`.


ldap.userPassword

The name of the LDAP attribute in the user's directory entry that contains the user's password. In Active Directory, `password` is the default name of the attribute.

```
ldap.userPassword=password
```

ldap.userEmail

The name of the LDAP attribute in the user's directory entry that contains the user's email address.

 **Note:** The **ldap.userEmail** property cannot have a null value. If your Active Directory Tree does not contain email information, a different attribute must be used. For example, **ldap.userEmail** might be set to **userPrincipalName**.

ldap.userRealm

Realm name that is used for user authentication. This setting is optional and can be commented out, in the `ldap.properties` file, for most configurations.


```
ldap.userRealm=users.company.domain.com
```

ldap.principalPattern

Pattern for construction of user principal for using LDAP authentication. Some LDAP servers require email address, for example, `userid@domain.com` and others require the user ID only. The string `{0}` is substituted by the users user ID entered at the login screen.

Searching for the users directory entry

The method available for finding the end-users information involves defining a starting point in the Active Directory tree and allowing BigFix Remote Control to recursively search through the tree for the userid. For most Active Directory implementations this is the preferred method as users are usually spread out in several locations in an Active Directory tree. This method is especially helpful if user information is contained under a single branch of the tree but broken up by department or underneath the branch

 **Note:** It should be noted that when LDAP has been enabled, new users and new user groups should be created in Active Directory and **not** in BigFix Remote Control. This is because each time the synchronization with Active Directory takes place the users and user groups are deleted from the BigFix Remote Control database and then imported again from Active Directory.

To use the recursive search configure the following parameters:

ldap.userBase

The base LDAP directory entry for looking up users that match the search criteria. If not specified, the search base is the top-level element in the directory context.

```
for example OU=mylocation,DC=mycompany,DC=com
```

You can refine your search by going deeper into the OU structure and selecting to search only within a specific organizational unit for example an OU called Users and therefore you would set the property value as

```
ldap.userBase=OU=Users,ou=mylocation,dc=mydomain,dc=mycompany,dc=com
```


This would instruct BigFix Remote Control to look for users matching the criteria, only within the Users OU (and any OUs that belong to the Users OU if ldap.groupSubtree is set to true)

ldap.userSearch

Defines the LDAP query that is used to import Active Directory users to BigFix Remote Control. The defined query needs to filter the results such that only those users which match the search criteria are imported to BigFix Remote Control. The default value is

(objectClass=user)

which means, look for users in any object that is a user object within the userbase. That is import all Active Directory users to BigFix Remote Control.

 **Note:** When using the above it should be noted that some environments can have thousands of users therefore it is important to create a filter which will only import the required users. To limit the users that are imported to only those users who match the search criteria and are members of the groups that were imported into BigFix Remote

Control through the **ldap.groupSearch** filter, you should set the property **ldap.userInGroup** to true. It should also be noted that as well as being imported into the relevant groups that are returned in the group search, users are also imported into the **DefaultGroup**. Setting **ldap.userInGroup** to false will import all users who match the search criteria, regardless of their group membership.

The search can therefore be further refined by using more complex queries. For example if you have the following values set

```
ldap.groupBase=(OU=mylocation.DC=mycompany.DC=com)
ldap.userSearch: (&(objectClass=user)(|(memberOf=CN=Department1,OU=GROUPS,
OU=mylocation,DC=mycompany,DC=com)(memberOf=CN=Department3,OU=GROUPS,
OU=mylocation,DC=mycompany,DC=com))(name={0}))
```

If there were three groups defined, Department1, Department2 and Department3 the above query would authenticate and import any users that are defined as objectclass user and are members of the Department1 OR Department3 groups. Users from Department2 would not be able to logon to BigFix Remote Control.

The (&(name={0})) is added to the end to specify that the name attribute is used for logging in. This value has to match whatever attribute was specified as ldap.userid.

ldap.userSubtree

Set this value to true if you want to recursively search the sub tree of the element specified by the userBase attribute for the user's directory entry. The default value of false causes only the top level to be searched (a nonrecursive search). This is ignored if you are using the userPattern expression.

```
ldap.userSubtree=true
```

Importing Active Directory Groups

One of the greatest benefits of integrating with Active Directory is being able to use existing Active Directory groups. After Active Directory groups are imported, an administrator must define the permissions for each group and group membership is handled inherently by Active Directory. To import Active Directory groups, configure the following properties in the `ldap.properties` file.

ldap.groupName

The LDAP attribute name that is used for the group search.

```
ldap.groupName=cn OR ldap.groupName=name
```

ldap.groupDescription

The LDAP attribute name to be used to get the description for the group. It is set to description by default.

```
ldap.groupDescription=description
```

ldap.groupNameTrim

Set to true or false. Limits the group name that is imported to the BigFix Remote Control database to 64 characters. The recommended value is false.

ldap.groupMembers

LDAP attribute name to be used to find the members of the groups that are returned as a result of the specified search. The default value is member.

```
ldapgroupMembers=member
```

ldap.groupSubtree

If set to true, BigFix Remote Control searches recursively through the subtree of the element that is specified in the **ldap.groupBase** parameter for groups that are associated with a user. If left unspecified, the default value of false causes only the top level to be searched, and no recursive search is run. True or False (default).

ldap.groupBase

The base LDAP directory entry for starting the search for groups to synchronize. If left unspecified, the default is to use the top-level element in the directory context.

```
for example OU=mylocation,DC=mycompany,DC=com
```

To refine your search and go deeper into the OU structure, select to start the search only within a specific organizational unit. For example, an OU called Test. Set the property to the following value.

```
OU=Test,OU=mylocation,DC=mycompany,DC=com
```

Therefore, BigFix Remote Control looks for groups that match the criteria, only within the Test OU (and any OUs that belong to the Test OU if **ldap.groupSubtree** is set to true).

ldap.groupSearch

Defines the LDAP query that is used to import AD groups to BigFix Remote Control. The defined query needs to filter the results such that only those groups that are needed are imported to BigFix Remote Control.

```
ldap.groupSearch=(objectClass=group)
```

Imports all AD groups found in the OU specified in the **ldap.groupBase** property to BigFix Remote Control. Some environment can have thousands of groups.

```
ldap.groupSearch=(&(objectClass=group)(cn=*SMS*))
```

Imports all groups that contain SMS in the **cn** attribute. For example, *visio-sms-users*.

```
ldap.groupSearch=(&(objectClass=group)(cn=admins))
```

Imports all groups that are named admins.

```
ldap.groupSearch=(&(objectClass=group)(cn=admins*))
```

Imports all groups that have the text admins in the name. For example, administrators, server-administrators.

ldap.groupMembers

LDAP attribute name to be used to find the members of the groups that are returned as a result of the specified search. The default value is member.


These queries can be tested by using the LDAP browsers directory search option or the LDAP configuration utility in the BigFix Remote Control server UI.

Testing the Connection

When the `common.properties` & `ldap.properties` files are updated, reset the BigFix Remote Control application by selecting **Admin > Reset Application**.

When the service restarts, log on to the BigFix Remote Control server by using an Active Directory user ID and password. If the entries in the LDAP properties file are correct, you are authenticated and logged on successfully.

BigFix Remote Control Server connects directly to LDAP. Therefore, any password changes within LDAP are immediately effective only if the LDAP password change synchronizes to the LDAP server that is set within the `ldap.properties` file.

 **Note:** The default ADMIN user ID within the BigFix Remote Control Server application always authenticates against the BigFix Remote Control Server regardless of whether LDAP authentication is enabled. If there is a connectivity problem between BigFix Remote Control Server and LDAP, the ADMIN user can always log on.

If there are any errors in the `ldap.properties` file, you see a failed logon message. The **Logon** screen is displayed with an Invalid user name or wrong password message.

To determine the cause of the failure look in the `trc.log` file. View the application log by using the server UI.

- In the BigFix Remote Control Server UI, click **Admin > View application log**
- Click **CTRL+END** to reach the end of the file.

The following common errors can be displayed. The errors indicate a problem with creating the initial connection between BigFix Remote Control Server and Active Directory.

AcceptSecurityContext error, data 525

Returns when user name is invalid.

AcceptSecurityContext error, data 52e

Returns when user name is valid but password or credentials are invalid. Prevents most other errors from being displayed as noted.

AcceptSecurityContext error, data 530

Logon failure: account logon time restriction violation. Displays only when presented with valid user name and password credentials.

AcceptSecurityContext error, data 531

Log on failure: user is not allowed to log on to this computer. Displays only when presented with valid user name and password credentials.

AcceptSecurityContext error, data 532

Logon failure: the specified account password is expired. Displays only when presented with valid user name and password credentials.

AcceptSecurityContext error, data 533

Logon failure: account currently disabled. Displays only when presented with valid user name and password credential.

AcceptSecurityContext error, data 701

The user's account is expired. Displays only when presented with valid user name and password credential.

AcceptSecurityContext error, data 773

The user's password must be changed before they log on for the first time. Displays only when presented with valid user name and password credential.

AcceptSecurityContext error, data 775

The referenced account is locked out and cannot be logged on to. Displays even if invalid password is presented.

LDAP Authentication.exceptionmyserver.mydomain.com:389

Displays when the server name specified by **ldap.connectionURL** is unreachable.

Verifying that the groups are imported

When authentication is successful and you are logged on to the BigFix Remote Control server, click **User groups > All User Groups** to verify that the correct groups were imported from Active Directory.

After the groups are imported into BigFix Remote Control, define permissions for the newly imported groups.

Sample LDAP Configuration File

The file is a sample configuration file. It uses a simple connection to Active Directory with importing of Active Directory groups

Licensed Materials - Property of IBM Corporation

5724-N88 5725-C431

(C) Copyright HCL Technologies Ltd. 2001, 2020

All Rights Reserved

US Government Users Restricted Rights - Use, duplication or

disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

LDAP Properties

Server Authentication definition

The directory URL used to establish an LDAP connection

ldap.connectionURL=ldap://myldapservers

define the secondary LDAP server name, if the primary is down we can use an alternative LDAP server

#-ldap.alternateURL=

The username used to authenticate a read-only LDAP connection. If left not set, an anonymous connection is made.

ldap.connectionName=administrator@mydomain.MyCompany.com

The password used to establish a read-only LDAP connection.

ldap.connectionPassword=myPassword

Instructs Remote Control to read the value of the password parameter as encrypted (true) or plain text (false). See Admin guide for instructions on generating encrypted password

ldap.connectionPasswordEncrypted=false

The fully qualified Java class name of the JNDI context factory to be used for
this connection. If left unset, the default JNDI LDAP provider class is used.

---**ldap.contextFactory=com.sun.jndi.ldap.LdapCtxFactory**

SASL Definition
#####

specifying the security level to use. Its value is one of the following strings: "simple" or "DIGEST-MD5".

. If using SSL, you have to use simple.

ldap.security_authentication=simple

#Identifies the realm or domain from which the connection name should be chosen

--- **ldap.connectionRealm=**

#Quality of protection

QOP can be one of: auth, auth-int, auth-conf

auth -- Authentication only

auth-int --Authentication and integrity checking by using signatures

auth-conf -- (SASL only) Authentication, integrity and confidentiality checking

by using signatures and encryption.

---**ldap.connectionQop=auth**

Number indicating the size of the largest buffer the server is able to receive when

using "auth-int" or "auth-conf". The default is 65536.

ldap.connectionMaxbuf=16384

```

# Strength can be one of: low,medium,high
# ---ldap.connectionStrength=high

##### SSL Definition
#####

# specifying the security protocol to use. Its value is a string determined by
# the service provider (for example: "ssl"). If this property is unspecified, the behaviour
# is determined by the service provider.
# ---ldap.security_protocol=ssl

# Access the keystore, this is where the Root CA public key cert was installed
# No need to specify the keystore password for read operations
# ---ldap.ssl_keyStore=PathOfKeyStoreFile
# ---ldap.ssl_keyStorePassword=KeystorePassword

# specifying how referrals encountered by the service provider are to be processed.
# The value of the property is one of the following strings:
# "follow" -- follow referrals automatically
# "ignore" -- ignore referrals
# "throw" -- throw ReferralException when a referral is encountered.
# If this property is not specified, the default is determined by the provider.
# ---ldap.referrals=follow

##### define Group search for LDAP #####

# The base LDAP directory entry for looking up group information. If left unspecified,
# the default is to use the top-level element in the directory context.
ldap.groupBase=OU=Groups,OU=mylocation,DC=mydomain,DC=mycompany,
DC=com

#The LDAP filter expression used for performing group searches.
ldap.groupSearch=(&(objectClass=group) (name=TRC*))

# Set to true if you want to recursively search the subtree of the element specified in
# the groupBase attribute for groups associated with a user. If left unspecified, the default

```

value of false causes only the top level to be searched (a nonrecursive search).

ldap.groupSubtree=true

#The LDAP attribute that we should use for group names.

ldap.groupName=name

#The LDAP attribute that we should use for group descriptions

ldap.groupDescription=description

This is the attribute specifying user members within a group

ldap.groupMembers=member

User search definition

#The base of the subtree containing users

#If not specified, the search base is the top-level context.

ldap.userBase=OU=Users,OU=mylocation,DC=mydomain,DC=mycompany, DC=com

The LDAP filter expression to use when searching for a user's directory entry, with {0} marking

where the actual username is inserted.

ldap.userSearch=(&(objectClass=User)(sAMAccountName={0}))

Set this value to true if you want to recursively search the subtree of the element specified by

the userBase attribute for the user's directory entry. The default value of false causes only the

top level to be searched (a nonrecursive search).

ldap.userSubtree=true

#Set this value to true if a user has to be a member of the groups found in the group search

ldap.userInGroup=true

Digest algorithm (SHA, MD2, or MD5 only)

Remote control will use it to encrypt the user input password and

compare it with password it receives from the LDAP server. If left unspecified, the default value is "cleartext".

--- **ldap.digest=SHA**

#LDAP attribute used for userids

ldap.userid=sAMAccountname

LDAP User password attribute

ldap.userPassword=password

LDAP Attribute containing the Users Email address

ldap.userEmail=userPrincipalName

If the following parameters are defined they are mapped into the local remote control database

ldap.forename=givenName

ldap.surname=sn

ldap.title=title

ldap.initials=initialsg

ldap.company=company

ldap.department=department

ldap.telephone=telephoneNumber

ldap.mobile=mobile

ldap.state=st

ldap.country=Co

Other property definitions

#Set this value to the page size of LDAP search retrievals (default=500).

Do not set this to anything greater than the max page size for the LDAP server (for example, AD has a limit of 1000)

ldap.page.size=500

Chapter 11. Federal information processing standard (FIPS 140-2) compliance in BigFix Remote Control

The US Federal information processing standard 140-2 (FIPS 140-2) is a cryptographic function validation program that defines security standards for cryptographic modules that are used in IT software. In FIPS 140-2 mode, BigFix Remote Control uses the FIPS 140-2 approved cryptographic providers; IBMJCEFIPS (certificate #1081), IBMJSSEFIPS (certificate 409), and OpenSSL FIPS Object Module (certificate #1747). The certificate for IBMJCEFIPS (certificate #1081) is held on the NIST website at <http://csrc.nist.gov/groups/STM/cmvp/documents/140-1/1401val2009.htm#1081>. The certificate for IBMJSSEFIPS (certificate 409) is held on the NIST website at <http://csrc.nist.gov/groups/STM/cmvp/documents/140-1/1401val2004.htm#409>. The certificate for OpenSSL FIPS Object Module (certificate #1747) is held on the NIST website at <http://csrc.nist.gov/groups/STM/cmvp/documents/140-1/1401val2012.htm#1747>. To enable FIPS for BigFix Remote Control you must configure all components, the server, controller, and target.

BigFix Remote Control version 9.x.x uses:

IBM Java JCE FIPS 140-2 Cryptographic Module version 1.3.1 Tested as meeting Level 1 with Windows XP Professional SP2 operating system that uses IBM JVM 1.6 (single-user mode) FIPS-approved algorithms:

- AES (Cert. #805);
- DSA (Cert. #297);
- HMAC (Cert. #445);
- RNG (Cert. #463);
- RSA (Cert. #387);
- SHS (Cert. #803);
- Triple-DES (Cert. #687).

IBM Java JSSE FIPS 140-2 Cryptographic Module version 1.1 Tested as meeting Level 1 with

- Windows 2000 Professional SP3 operating system (JVM 1.3.1_03 and JVM 1.4.1_04), Windows 2000 Advanced Server SP4 operating system (JVM 1.4.1)
- Sun Solaris 5.8 (JVM 1.3.1 and 1.4.1)
- AIX 5.2 (JVM 1.3.1 and 1.4.1)
- SuSE Linux Enterprise Server 8 (JVM 1.4.1_05)
- Red Hat Linux Advanced Server 2.1(JVM 1.4.1_05)
- IBM OS/400® V5R2M0 (JVM 1.4.1)

- z/OSV1R4 (JVM 1.4.1)

FIPS-approved algorithms:

- SHA-1 (Cert. #148);
- Triple-DES (Cert. #163);
- AES (Cert. #53);
- DSA (Cert. #83);
- RSA (PKCS#1, vendor affirmed);
- HMAC-SHA-1 (Cert. #148, vendor affirmed);

OpenSSL FIPS Object Module version 2.0.2 Tested as meeting Level 1 with

- Android
 - Android 2.2 (gcc Compiler Version 4.4.0);
 - Android 2.2 running on Qualcomm QSD8250 (ARMv7) with NEON (gcc Compiler Version 4.4.0);
 - Android 2.2 running on OMAP 3530 (ARMv7) with NEON (gcc Compiler Version 4.1.0);
 - Android 3.0 (gcc Compiler Version 4.4.0);
 - Android 4.0 (gcc Compiler Version 4.4.3);
 - Android 4.0 running on TI OMAP 3 (ARMv7) with NEON (gcc Compiler Version 4.4.3);
 - Android 4.1 running on TI DM3730 (ARMv7) (gcc Compiler Version 4.6);
 - Android 4.1 running on TI DM3730 (ARMv7) with NEON (gcc Compiler Version 4.6);
 - Android 4.2 running on Nvidia Tegra 3 (ARMv7) (gcc Compiler Version 4.6);
 - Android 4.2 running on Nvidia Tegra 3 (ARMv7) with Neon (gcc Compiler Version 4.6) (single-user mode).
- Microsoft Windows 7
 - Microsoft Windows 7 (32-bit) (Microsoft 32-bit C/C++ Optimizing Compiler Version 16.00);
 - Microsoft Windows 7 (64 bit) (Microsoft C/C++ Optimizing Compiler Version 16.00);
 - Microsoft Windows 7 running on Intel Core i5-2430M (64-bit) with AES-NI (Microsoft® C/C++ Optimizing Compiler Version 16.00 for x64);
- Microsoft Windows 2008
 - Microsoft Windows 2008 running on Intel Xeon™ E3-1220v2 (32-bit under vSphere) (Microsoft 32-bit C/C++ Optimizing Compiler Version 16.00 for 80x86);
 - Microsoft Windows 2008 running on Intel Xeon E3-1220v2 (64-bit under vSphere) (Microsoft C/C++ Optimizing Compiler Version 16.00 for x64);
- uCLinux 0.9.29 (gcc Compiler Version 4.2.1);
- Fedora 14 running on Intel Core i5 with AES-NI (gcc Compiler Version 4.5.1);
- HP-UX 11i (32 bit) (HP C/aC++ B3910B); HP-UX 11i (64 bit) (HP C/aC++ B3910B);

- Ubuntu 10.04
 - Ubuntu 10.04 (32 bit) (gcc Compiler Version 4.1.3);
 - Ubuntu 10.04 (64 bit) (gcc Compiler Version 4.1.3);
 - Ubuntu 10.04 running on Intel Core i5 with AES-NI (32 bit) (gcc Compiler Version 4.1.3);
- Linux
 - Linux 2.6 (gcc Compiler Version 4.3.2);
 - Linux 2.6.27 (gcc Compiler Version 4.2.4);
 - Linux 2.6.32 (gcc Compiler Version 4.3.2);
 - Linux 2.6.33 (gcc Compiler Version 4.1.0);
 - Linux 2.6 (gcc Compiler Version 4.1.0);
- VxWorks 6.8 (gcc Compiler Version 4.1.2);
- Oracle Solaris
 - Oracle Solaris 10 (32 bit) (gcc Compiler Version 3.4.3);
 - Oracle Solaris 10 (64 bit) (gcc Compiler Version 3.4.3);
 - Oracle Solaris 11(32 bit) (gcc Compiler Version 4.5.2);
 - Oracle Solaris 11 (64 bit) (gcc Compiler Version 4.5.2);
 - Oracle Solaris 11 running on Intel Xeon 5675 with AES-NI (32 bit) (gcc Compiler Version 4.5.2);
 - Oracle Solaris 11 running on Intel Xeon 5675 with AES-NI (64 bit) (gcc Compiler Version 4.5.2);
 - Oracle Solaris 11 (32 bit) (Sun C Version 5.12); Oracle Solaris 11 (64 bit) (Sun C Version 5.12);
- Oracle Linux
 - Oracle Linux 5 (64 bit) (gcc Compiler Version 4.1.2);
 - Oracle Linux 5 running on Intel Xeon 5675 with AES-NI (gcc Compiler Version 4.1.2);
 - Oracle Linux 6 (gcc Compiler Version 4.4.6);
 - Oracle Linux 6 running on Intel Xeon 5675 with AES-NI (gcc Compiler Version 4.4.6);
- CascadeOS 6.1 (32 bit) (gcc Compiler Version 4.4.5); CascadeOS 6.1 (64 bit) (gcc Compiler Version 4.4.5);
- Apple iOS 5.1 (gcc Compiler Version 4.2.1);
- Microsoft Windows CE 6.0 (Microsoft C/C++ Optimizing Compiler Version 15.00 for ARM); Microsoft Windows CE 5.0 (Microsoft C/C++ Optimizing Compiler Version 13.10 for ARM);
- DSP Media Framework 1.4 (TMS320C6x C/C++ Compiler v6.0.13);
- NetBSD 5.1 (gcc Compiler Version 4.1.3);
- RHEL 6
 - RHEL 6 running on Intel Xeon E3-1220v2 (32-bit under vSphere) (gcc Compiler Version 4.4.6);
 - RHEL 6 running on Intel Xeon E3-1220v2 (64-bit under vSphere) (gcc Compiler Version 4.4.6);

FIPS-approved algorithms:

- AES (Certs. #1884, #2116, and #2234);

- DRBG (Certs. #157, #229, and #264);
- DSA (Certs. #589, #661, and #693);
- HMAC (Certs. #1126, #1288, and #1363);
- RNG (Certs. #985, #1087, and #1119);
- RSA (Certs. #960, #1086, and #1145);
- SHS (Certs. #1655, #1840, and #1923);
- Triple-DES (Certs. #1223, #1346, and #1398);
- ECDSA (Certs. #264, #270, #315, #347 and #378);
- CVL (Certs. #10, #12, #24, #36 and #49).

Enable FIPS compliance on the server

Enabling FIPS compliance on a server installation with a stand-alone WebSphere Application Server

The BigFix Remote Control Server uses the middleware infrastructure that is provided by WebSphere secure HTTP communications. Therefore, to enable FIPS for a manual BigFix Remote Control Server installation requires that you configure WebSphere for FIPS-compliant mode. You must also configure the BigFix Remote Control Server through a setting in the `common.properties` configuration file.


To enable FIPS compliance for a manual installation, complete the following steps:

1. Configure WebSphere


The WebSphere documentation describes how to enable FIPS mode in WebSphere.

- WebSphere Application Server:
 - v7.0: http://pic.dhe.ibm.com/infocenter/wasinfo/v7r0/index.jsp?topic=/com.ibm.websphere.base.doc/info/aes/ae/tsec_fips.html
 - v8.5: http://pic.dhe.ibm.com/infocenter/wasinfo/v6r1/index.jsp?topic=/com.ibm.websphere.base.doc/info/aes/ae/tsec_fips.html
- WebSphere Application Server Network Deployment:
 - v7.0: http://pic.dhe.ibm.com/infocenter/wasinfo/v7r0/index.jsp?topic=/com.ibm.websphere.nd.doc/info/ae/ae/rovr_fips.html
 - v8.5: http://pic.dhe.ibm.com/infocenter/wasinfo/v8r5/index.jsp?topic=%2Fcom.ibm.websphere.nd.doc%2Fae%2Ftsec_fips.html
- WebSphere Application Server - Express™:
 - v7.0: http://pic.dhe.ibm.com/infocenter/wasinfo/v7r0/index.jsp?topic=/com.ibm.websphere.express.doc/info/exp/ae/tsec_fips.html

- v8.5:http://pic.dhe.ibm.com/infocenter/wasinfo/v8r5/index.jsp?topic=%2Fcom.ibm.websphere.express.doc%2Fae%2Ftsec_fips.html

 **Note:** Running in FIPS mode in IBM WebSphere with the IBM JRE and the IBM JSSE provider currently does not work when you use an MS SQL database. These options work with MS SQL when FIPS is not enabled in IBM WebSphere.

2. Log on to the BigFix Remote Control Server with a valid admin ID and password.
3. Click **Admin > Edit properties files**
4. In the `common.properties` file set **FIPS.compliance** to true.
5. Click **Submit**.
6. Click **Admin > Reset Application**.

 **Note:** The FIPS enablement changes in WebSphere affect all other applications that are running on the server. Therefore, browser settings for the users who access the other applications must be changed to support Transport Layer Security (TLS), if required by their browser version.

For example, to enable TLS in Internet Explorer complete the following steps:

- Click **Tools > Internet Options**.
- On the **Advanced** tab, select **Use TLS 1.0**.
- Click **Apply**
- Click **OK**.

Enabling FIPS compliance on an automated server installation

To enable FIPS compliance on an automated BigFix Remote Control Server installation, complete the following steps:

1. Edit the `java.security` file that is found at the following directory.

Windows systems

```
%TRC_SERVER_PATH%\java\jre\lib\security\java.security
```

Where `%TRC_SERVER_PATH%` is the path for the installation directory for the BigFix Remote Control Server.

Linux / UNIX systems

```
$TRC_SERVER_PATH/java/jre/lib/security/java.security
```

Where `$TRC_SERVER_PATH` is the path for the installation directory for the BigFix Remote Control Server.

2. Modify the `security.provider.x=` list so the following entry is the first one in the list:

```
security.provider.1=com.ibm.crypto.FIPS.provider.IBMJCEFIPS
```

```
security.provider.1=com.ibm.fips.jsse.IBMJSSEFIPS
```

```
security.provider.2=com.ibm.crypto.fips.provider.IBMJCEFIPS
```

Fix the number sequence of the other items in this list so that all items are numbered in sequence.

For example, the full list after the changes is as follows:

```
security.provider.1=com.ibm.fips.jsse.IBMJSSEFIPS
```

```
security.provider.2=com.ibm.crypto.fips.provider.IBMJCEFIPS
```

```
security.provider.3=com.ibm.jsse2.IBMJSSEProvider2
```

```
security.provider.4=com.ibm.crypto.provider.IBMJCE
```

```
security.provider.5=com.ibm.security.jgss.IBMJGSSProvider
```

```
security.provider.6=com.ibm.security.cert.IBMCertPath
```

```
security.provider.7=com.ibm.security.sasl.IBMSASL
```

```
security.provider.8=com.ibm.xml.crypto.IBMXMLCryptoProvider
```

```
security.provider.9=com.ibm.xml.enc.IBMXMLEncProvider
```

```
security.provider.10=com.ibm.security.jgss.mech.spnego.IBMSPNEGO
```

```
security.provider.11=sun.security.provider.Sun
```

```
security.provider.1=com.ibm.crypto.FIPS.provider.IBMJCEFIPS
```

```
security.provider.2=com.ibm.crypto.provider.IBMJCE
```

```
security.provider.3=com.ibm.jsse.IBMJSSEProvider
```

```
security.provider.4=com.ibm.jsse2.IBMJSSEProvider2
```

```
security.provider.5=com.ibm.security.jgss.IBMJGSSProvider
```

```
security.provider.6=com.ibm.security.cert.IBMCertPath
```

```
security.provider.7=com.ibm.crypto.pkcs11impl.provider.IBMPKCS11Impl
```

```
security.provider.8=com.ibm.security.cmskeystore.CMSProvider
```

```
security.provider.9=com.ibm.security.jgss.mech.spnego.IBMSPNEGO
```

```
security.provider.10=com.ibm.security.sasl.IBMSASL
```

```
security.provider.11=com.ibm.xml.crypto.IBMXMLCryptoProvider
```

```
security.provider.12=com.ibm.xml.enc.IBMXMLEncProvider
```

```
security.provider.13=org.apache.harmony.security.provider.PolicyProvider
```

3. Save the file.

4. Edit the `jvm.options` file and add a new line, `-Dcom.ibm.jsse2.usefipsprovider=true`.

Windows systems

```
%TRC_SERVER_PATH% \wlp\usr\servers\trcserver\jvm.options
```

Where `%TRC_SERVER_PATH%` is the path for the installation directory for the BigFix Remote Control Server.

Linux / UNIX systems

```
$TRC_SERVER_PATH/wlp/usr/servers/trcserver/jvm.options
```

Where `$TRC_SERVER_PATH` is the path for the installation directory for the BigFix Remote Control Server.

5. Log on to the BigFix Remote Control Server with a valid admin ID and password.
6. Click **Admin > Edit properties files**
7. In the `common.properties` file set **FIPS.compliance** to true.
8. Click **Submit**.
9. Click **Admin > Reset Application**. Restart the server service.

Check to see whether the BigFix Remote Control Server is configured for FIPS by completing the following step.

- Click **Admin > View Current Server Status**.

The following fields show that FIPS compliance is enabled.

- Enabled FIPS mode: - The value of this field is determined by the **FIPS.compliance** property in the `common.properties` file.
- JVM configured for FIPS: - The value of this field is determined by the configuration of the JVM and the security providers that are listed in the `java.security` file.


Enabling FIPS compliance on the controller

The BigFix Remote Control controller is a Java application that requires a FIPS certified cryptographic provider when FIPS compliance is enabled. Only the IBM Java Runtime Environment (JRE) is supported in FIPS-compliant mode.

The IBM JRE for Windows operating system and Linux (Intel) operating systems is included with BigFix Remote Control and is installed when you install the controller software.

If you are using Windows operating system, the JRE is included in the controller package `trc_controller_setup.exe` and `trc_controller.msi`. For Linux operating system, the JRE is included in the package `ibm-trc-controller-jre-9.x.x.i386.rpm`. Where 9.x.x is the version that you want to install. For example, 9.1.0. These packages install the IBM Java Runtime Environment pre-configured with the IBM FIPS certified cryptographic provider. They also register the MIME type `application/x-ibm-trc-jws` and a file association for `*.trcjws` files. The file types are used by the BigFix Remote Control server in FIPS-compliant mode to start the controller. For more information about installation instructions for the controller, see [Install the controller \(on page 95\)](#).

To use a different installation of the IBM JRE, the BigFix Remote Control controller uses the FIPS-compliant cryptography module that is included with the IBM Java virtual machine. To enable FIPS mode, the settings of the JVM (Java virtual machine) that are used to run the controller need to be modified. When you enable FIPS compliance, any other Java applications that are running on the default JVM can also use the FIPS provider and the other security providers that are listed in the `java.security` file.

 **Note:** Enabling FIPS on the controller is not supported if you are using an Oracle JVM.

To enable FIPS compliance on the controller if you are not using the version of IBM JRE supplied with BigFix Remote Control, complete the following steps:

1. Edit the `java.security` file

Windows systems

```
%JRE_HOME%\lib\security\java.security
```

Where `%JRE_HOME%` is the path to the directory where the Java virtual machines Java Runtime Environment (JRE) is installed.

Linux / UNIX systems

```
$JRE_HOME/lib/security/java.security
```

Where `$JRE_HOME` is the path to the directory where the Java virtual machines Java Runtime Environment (JRE) is installed.

2. Modify the **security.provider.x= list** so that the following two entries are the first ones in the list:

```
security.provider.1=com.ibm.fips.jsse.IBMJSSEFIPS  
security.provider.2=com.ibm.crypto.fips.provider.IBMJCEFIPS
```

Fix the number sequence of the other items in this list so that all items are numbered in sequence. For example,

```
security.provider.1=com.ibm.fips.jsse.IBMJSSEFIPS
security.provider.2=com.ibm.crypto.fips.provider.IBMJCEFIPS
security.provider.3=com.ibm.jsse2.IBMJSSEProvider2
security.provider.4=com.ibm.crypto.provider.IBMJCE
security.provider.5=com.ibm.security.jgss.IBMJGSSProvider
security.provider.6=com.ibm.security.cert.IBMCertPath
security.provider.7=com.ibm.security.sasl.IBMSASL
security.provider.8=com.ibm.xml.crypto.IBMXMLCryptoProvider
security.provider.9=com.ibm.xml.enc.IBMXMLEncProvider
security.provider.10=org.apache.harmony.security.provider.PolicyProvider
security.provider.11=com.ibm.security.jgss.mech.spnego.IBMSPNego
```

 **Note:**

- a. Applies to all supported versions of the IBM JVM.
- b. You must make a file association for the *.trcjws files before you start the first session with a target. Use the following commands

Windows systems

```
%JRE_HOME%\jre\bin\javaws
```

Where %JRE_HOME% is the path to the directory where the Java virtual machines Java Runtime Environment (JRE) is installed.

Linux / UNIX systems


```
$JRE_HOME/jre/bin/javaws.exe
```

Where \$JRE_HOME is the path to the directory where the Java virtual machines Java Runtime Environment (JRE) is installed.

Check to see whether the controller is configured for FIPS by completing the following step during a remote control session.

- Click **Controller tools > Show session information** in the controller window.

Edit the `trc_controller.cfg` file on the system that the controller is installed on.

 **Note:** Only required if you are running the controller locally for establishing peer to peer sessions. For more information about installing the controller to your local system, see [Install the controller \(on page 95\)](#).

Windows systems

```
[controller install dir]\trc_controller.cfg
```

Where *[controller install dir]* is the installation directory that is chosen when you install the controller.

Linux systems

```
/opt/ibm/trc/controller/trc_controller.cfg
```

Set the **fips.compliance** property to true and save the file.

Enable FIPS compliance on the target

The BigFix Remote Control target includes FIPS-capable OpenSSL libraries. You can enable FIPS compliance at installation time or by editing the target registry on a Windows system or by changing the configuration file on a Linux system.

For more information about installing the target, see the BigFix Remote Control Installation Guide.

Using the target user interface, choose the appropriate option to verify that the target is in FIPS mode.

- On the BigFix Remote Control- Target user interface, click **Actions Menu > Connection info**
- Hover the mouse over the **BigFix Remote Control** icon in the system notification area.

Enabling FIPS compliance on a Windows target

On a Windows system, you can enable FIPS compliance on the target in two ways; during installation or by editing the target registry after installation.

Enabling FIPS compliance by using the target installer

Enable the FIPS compliance target property during installation by completing the following steps:

1. On the **Server Address** panel of the target installer, click **Advanced settings**.
2. Select **Use a FIPS certified cryptographic provider** and **Use secure connections (https)**. Continue with the rest of the target installation.

Performing a silent installation

When performing a silent target installation, run the installation command and use the **FIPSCOMPLIANCE** property to enable FIPS on the target . For more details of performing a silent installation, see [Running a target custom installation on a Windows system \(on page 85\)](#).

Use the following properties when enabling FIPS mode

- TRC_SERVER_PROTOCOL=https
- TRC_SERVER_PORT=443
- FIPSCOMPLIANCE=yes

For example : `trc_target_setup.exe /s /v"/qn TRC_SERVER_HOSTNAME=yourserver TRC_SERVER_PROTOCOL=https TRC_SERVER_PORT=443 FIPSCOMPLIANCE=yes"`

where **yourserver** is the hostname or IP address of your BigFix Remote Control Server.

Enabling FIPS compliance after target installation

After you install the BigFix Remote Control target, you can enable FIPS compliance by editing the target registry. To enable FIPS compliance, complete the following steps.

1. Run the `regedit` command at a command prompt window.
2. In the Windows registry, go to `HKEY_LOCAL_MACHINE\SOFTWARE\IBM\Tivoli\Remote Control\Target`
3. Right-click **FIPSCompliance** and select **Modify**.
4. Type `yes` in the **Value data** field and click **OK**.
5. Restart the target service.

For more information about restarting the target service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Enabling FIPS compliance in Linux or UNIX based operating systems

After you install the BigFix Remote Control target, you can enable FIPS compliance by editing the `ibmtrct.conf` file. To enable FIPS compliance, complete the following steps:

1. Edit the `/etc/ibmtrct.conf` file.

2. Set the value of *FIPSCompliance* to yes and save the file.

3. Restart the target service.

For more information about restarting the target service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Enabling FIPS compliance on the gateway

You can enable FIPS compliance on the gateway component by editing the gateway configuration file that is created when you install gateway support.

The `trc_gateway.properties` file is in the following directory.

Windows systems

```
\Documents and Settings\All Users\Application Data\IBM\Tivoli\Remote Control\Gateway
```

```
or \ProgramData\IBM\Tivoli\Remote Control\Gateway.
```

Linux systems

```
/etc
```

To enable FIPS compliance, complete the following steps.

1. Edit the `trc_gateway.properties` file.

2. Set **FIPSCompliance = Yes**.

3. Save the file.

4. Restart the gateway service.

For more information about restarting the gateway service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Enabling FIPS compliance on the broker

You can enable FIPS compliance on the broker component by editing the broker configuration file that is created when you install broker support.

The `trc_broker.properties` file is in the following directory.

Windows systems

`\Documents and Settings\All Users\Application Data\IBM\Tivoli\Remote Control\broker.`

or `\ProgramData\IBM\Tivoli\Remote Control\broker.`

Linux systems

`/etc`

To enable FIPS compliance, complete the following steps.

1. Edit the `trc_broker.properties` file.
2. Set **FIPSCompliance = Yes**.
3. Save the file.
4. Restart the broker service.

For more information about restarting the broker service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Chapter 12. NIST SP800-131A compliance in BigFix Remote Control

BigFix Remote Control version 9.1.0 components can be configured for NIST SP800-131A compliance.

The National Institute of Standards and Technology (NIST) Special Publications (SP) 800-131A standard strengthens algorithms and increases the cryptographic key lengths to improve security.

The following prerequisites are required:

- Ensure that all keys have at least a key security strength greater than or equal to 112 bits. RSA keys must be at least 2048 bits.
- Ensure that all certificates are created with the new key strengths. Any RSA certificates that use keys shorter than 2048 bits must be replaced with a certificate that uses 2048-bit keys or higher.
- Ensure that all certificates are signed by an allowed signature algorithm of minimum SHA-2.

When you enable NIST SP800-131A compliance, the TLSv1.2 protocol is used for providing secure connections. Therefore, you must ensure that your browser is compatible.


Table 19. Browser compatibility for TLSv1.2

The following table provides information about the supported browser versions that are compatible with TLSv1.2.

	TLSv1.2 not supported	TLSv1.2 supported but disabled but default	TLSv1.2 supported and enabled by default
Internet Explorer	All versions of IE on Windows XP and Windows Vista operating systems (IE6, IE7, IE8, IE9)	IE8, IE9, IE10 on Windows 7 and Windows 8 operating system.	IE11 on Windows 7 operating system and later
Firefox	<24	24	None

Compliance with NIST SP800-131A also requires that the cryptographic provider is FIPS 140-2 certified. When SP800-131A compliance is enabled, FIPS 140-2 compliance is enabled automatically, even when it is disabled in the settings.

For NIST SP800-131A compliance, you must configure all your components. There is no compatibility with earlier versions of the components.

 **Note:** There is no support for NIST SP800-131A with Oracle JVMs. Therefore, to take advantage of the NIST support, you must install the stand-alone controller component.

Enable NIST SP800-131A compliance on the server

You can enable NIST SP800-131A compliance on the BigFix Remote Control server during installation, when you are using the server installer program. You can also enable NIST compliance after installation. To enable NIST SP800-131A compliance for a manual BigFix Remote Control Server installation, you must configure the BigFix Remote Control Server and WebSphere.

Enabling NIST SP800-131A compliance during the server installation

To enable NIST SP800-131A compliance during installation, follow the instructions in [Installing by using the server installer \(on page 32\)](#). Select **Enable NIST SP800-131A compliance (Enables FIPS)** on the **Web server parameters** pane during the installation.

Enabling NIST SP800-131A compliance on a server with a stand-alone WebSphere Application Server

The BigFix Remote Control Server uses the middleware infrastructure that is provided by WebSphere secure HTTP communications. Therefore, to enable NIST SP800-131A compliance for a manual BigFix Remote Control Server installation you must configure BigFix Remote Control Server and WebSphere.


To enable NIST SP800-131A compliance for a manual server installation, complete the following steps after you install the server.

1. Configure WebSphere

The WebSphere documentation describes how to enable NIST SP800-131A in WebSphere. Follow the instructions relevant to your version of WebSphere.

- WebSphere Application Server:
 - v7.0: http://pic.dhe.ibm.com/infocenter/wasinfo/v7r0/topic/com.ibm.websphere.base.doc/info/aes/ae/tsec_config_strictsp300.html
 - v8.5: http://pic.dhe.ibm.com/infocenter/wasinfo/v8r5/topic/com.ibm.websphere.base.iseries.doc/ae/tsec_config_strictsp300.html
- WebSphere Application Server Network Deployment:
 - v7.0: http://pic.dhe.ibm.com/infocenter/wasinfo/v7r0/topic/com.ibm.websphere.nd.doc/info/ae/ae/tsec_config_strictsp300.html

- v8.5: http://pic.dhe.ibm.com/infocenter/wasinfo/v8r5/topic/com.ibm.websphere.nd.doc/ae/tsec_config_strictsp300.html
 - WebSphere Application Server - Express:
 - v7.0: http://pic.dhe.ibm.com/infocenter/wasinfo/v7r0/topic/com.ibm.websphere.express.doc/info/exp/ae/tsec_config_strictsp300.html
 - v8.5: http://pic.dhe.ibm.com/infocenter/wasinfo/v8r5/topic/com.ibm.websphere.express.iseries.doc/ae/tsec_config_strictsp300.html
2. Log on to the BigFix Remote Control Server with a valid admin ID and password.
 3. Click **Admin > Edit properties files**
 4. In the `common.properties` file set `sp800131a.compliance` to true.
 5. Click **Submit**.
 6. Click **Admin > Reset Application**.
 7. Restart the server service.
For more information about restarting the server service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

 **Note:** NIST SP800-131A enablement changes in WebSphere affect all other applications that are running on that server. Therefore, browser settings for the users who access those other applications must be changed to support Transport Layer Security (TLS).

To enable TLS in Internet Explorer, complete the following steps.

- Click **Tools > Internet Options**.
- On the **Advanced** tab, select **Use TLS 1.2**.
- Click **Apply**.
- Click **OK**.

To enable TLS in Firefox, complete the following steps.

- In the browser, go to the **about:config** page.
- Click **I'll be careful, I promise**.
- In the search field search for **security.tls.version.max**.
- Set the value to 3.

Enabling NIST SP800-131A compliance after you install the server

After you install the server by using the installer program, you can enable NIST SP800-131A compliance in a number of ways.

However, if you did not already enable FIPS you must enable it first. For more information about enabling FIPS after you install the server, see [Enabling FIPS compliance on an automated server installation \(on page 154\)](#).

You must also make sure that the server certificate is compliant by ensuring that you follow the prerequisites for NIST support. For more information about certificate prerequisites, see [NIST SP800-131A compliance in BigFix Remote Control \(on page 163\)](#).

To enable NIST SP800-131A compliance after an automated BigFix Remote Control Server installation, complete the following steps.

1. Choose the appropriate method for enabling the NIST configuration.

Option 1

- a. Go to the tools directory that is in the server installation directory.
- b. Edit the `trcsetup.cmd` or `trcsetup.sh` file, depending on your operating system.
- c. In the line that calls the `ssl.cmd` or `ssl.sh` file, change the 0 that is before `trc` to a 1. Change the 0 that is at the end of the command to a 1 also. For example,

The command before the change is,

```
..\tools\ssl.cmd" "C:\Program Files (x86)\IBM\Tivoli\TRC\server"
1 0 "C:\ " "%CERTSTOREPW%" "servername.localnet" 0 trc
"%CERTSTOREPWSELF%" "TrC" "0"

..\tools\ssl.cmd" "C:\Program Files (x86)\IBM\Tivoli\TRCServer"
1 0 "C:\ " "%CERTSTOREPW%" "servername.localnet" 0 trc
"%CERTSTOREPWSELF%" "TrC" "0"
```

The command after the change is,


```
..\tools\ssl.cmd" "C:\Program Files (x86)\IBM\Tivoli\TRC\server"
1 0 "C:\ " "%CERTSTOREPW%" "servername.localnet" 1 trc
"%CERTSTOREPWSELF%" "TrC" "1"

..\tools\ssl.cmd" "C:\Program Files (x86)\IBM\Tivoli\TRCServer"
1 0 "C:\ " "%CERTSTOREPW%" "servername.localnet" 1 trc
"%CERTSTOREPWSELF%" "TrC" "1"
```

- d. Save the file.
- e. In the same directory, edit `tmem.sh` or `tmem.cmd`, depending on your operating system.
- f. Set the value of **NIST800=1**. Set the value of **FIPSON=1** if it is not already set.
- g. Run the following command.


```
trcsetup userid password certpassword
```

Where *userid* and *password* are the database connection credentials and *certpassword* is your certificate file password.

 **Note:** Derby does not have database credentials, therefore use `userid` and `password` for the credentials. Type the following command when you are using Derby.

```
trcsetup userid password certpassword
```

Option 2 - Temporary NIST configuration

 **Note:** The configuration changes set in this option are overwritten if you run the `trcsetup` or `tmem` files again.

- a. Edit the `ssl.xml` file that is in the `[installdir]\wlp\usr\servers\trcserver` directory.

Where

[installdir]

Is the server installation directory.

- b. Add **`sslProtocol="TLSv1.2"`** to the line **`ssl id="defaultSSLConfig"`**. For example,

```
<server>
<ssl id="defaultSSLConfig" sslProtocol="TLSv1.2"
/>
<keystore id="defaultKeyStore" password="TrCWebAS"
/>
</server>
```

- c. Save the `ssl.xml` file.
- d. In the same directory, edit the `jvm.options` file.
- e. Add the lines, **`-Dcom.ibm.jsse2.sp800-131=strict`** and **`-Dcom.ibm.jsse2.overrideDefaultTLS=true`**.
- f. Add the line, **`-Dcom.ibm.jsse2.sp800-131=strict`**.
- g. Save the file.

2. Log on to the BigFix Remote Control Server with a valid admin ID and password.
3. Click **Admin > Edit properties files**
4. In the `common.properties` file, set **sp800131a.compliance** to true.
5. Click **Submit**.
6. Click **Admin > Reset Application**. Restart the server service.
For more information about restarting the server service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Check to see whether the BigFix Remote Control Server is configured for NIST SP800-131A by completing the following step.

- Click **Admin > View Current Server Status**.


The following fields show that NIST SP800-131A compliance is enabled.

- Enabled NIST SP800-131A mode
- JVM configured for NIST SP800-131A mode

Creating a certificate for an MS SQL database when NIST SP800-131A is enabled

When you enable NIST SP800-131A compliance and you are using an MS SQL database, you must create a certificate.

To generate the certificate, you can use the IBM Key Management tool. You can access the IBM Key Management tool if the BigFix Remote Control server is installed with embedded components and also if the controller component is installed. It is also provided by IBM WebSphere Application Server.

 **Note:** To create a certificate with 4096 key size or greater, you must overwrite the restriction policy files `local_policy.jar` and `US_export_policy.jar`.

Go to the following directory and copy the `local_policy.jar` and `US_export_policy.jar` files.

Windows systems

```
TRC\server\java\demo\jce\policy-files\unrestricted
```

Linux systems

```
TRC/server/java/demo/jce/policy-files/unrestricted
```


Replace the following files with the JAR files that you copied.

Windows systems

```
TRC\server\java\jre\lib\security\local_policy.jar
```

```
TRC\server\java\jre\lib\security\US_export_policy.jar
```

Linux systems

```
TRC/server/java/jre/lib/security/local_policy.jar
```

```
TRC/server/java/jre/lib/security/US_export_policy.jar
```

To create and install the certificate, complete the following steps:

1. Install one of the supported versions of MS SQL server and the latest patches. Minimum requirement is MS SQL Server 2012 Service Pack 3.
2. Create a keystore with a self-signed certificate.
 - a. Open a command line window.
 - b. Go to one of the following directories to run the keytool.

Remote control server that is installed with embedded components

Go to the BigFix Remote Control server installation directory.

WebSphere Application Server is installed

Go to the WebSphere Application Server installation directory.

The controller component is installed

Go to the `...\Controller\jre` directory. For example,

Windows systems.

```
C:\Program Files\IBM\tivoli\Remote Control  
\Controller\jre
```

Linux systems.

```
/opt/ibm/trc/controller/jre
```

- c. Change to the `bin` directory.
- d. Run the `ikeyman` file relevant to your operating system.

Windows systems

```
ikeyman.bat
```

Linux systems

```
ikeyman.sh
```

- e. Select **Key Database File > New**
 - f. Select **PKCS12** for **Key database type**.
 - g. Click **Browse** and go to the location in which you want to store the keystore.
 - h. Type a file name for your file and click **Save**.
 - i. Click **OK**.
 - j. Enter and confirm a password to protect the keystore and click **OK**.
 - k. Select **Create > New Self-Signed Certificate**
 - l. Enter a name for the **Key Label**.
For example, the host name of the server.
 - m. Select **X509 V3** for the **Version**.
 - n. Select a **Key Size** value.
Recommended value for NIST SP800-131A compliance is 2048 or greater.
 - o. Select **SHA256WithRSA** for the **Signature Algorithm**
 - p. Type a **Common Name**.
Set to the DNS host name of your server.
For example, `trcserver.example.com`.
 - q. Enter any additional optional information as required.
 - r. Enter a **Validity Period**.
Set the number of days that the certificate is valid for. Default is 365 days.
 - s. Set the **Subject Alternative Names, DNS Name** option to the DNS host name of your server.
 - t. Click **OK**.
3. Add the certificate store to the database server.
 - a. At a command line, run `mmc.exe`.
 - b. Add a certificate snap-in.

- i. Select **File > Add/Remove Snap-in**.
 - ii. Select the **Certificates** snap-in and click **Add**.
 - iii. Select **Computer account** and click **Next**.
 - iv. Ensure that the **Local computer** option is selected and click **Finish**.
 - v. Click **OK**.
 - c. Import the certificate
 - i. In the **Console1** window, go to **Console Root > Certificates**.
 - ii. Right click **Certificates** and select **All Tasks > Import**.
 - iii. Click **Next** on the **Welcome** window.
 - iv. Click **Browse** and select the certificate store that you created.
 - v. Click **Next**.
 - vi. Enter the password for the certificate store and click **Next**.
 - vii. Ensure that **Place all certificated in the following store** is selected and that **Certificate Store** is set to **Personal**. Click **Next**.
 - viii. Click **Finish**.
4. Manage private keys.
 - a. Right-click the certificate file and select **All Tasks > Manage Private Keys**.
 - b. Click **Add**.
 - c. Click **Check Names**, select **MSSQLSERVER** and click **OK**.
 - d. Click **OK** on the **Select Users and Groups** window.
 - e. Set permissions for **MSSQLSERVER** on the **Permissions** window and click **OK**. For example, select **Allow** for **Read** for a Read-only option.
5. To complete the configuration, run the SQL Server Configuration Manager.
 - a. Expand **SQL Server Network Configuration**.
 - b. Right click **Protocols for MSSQLSERVER** and select **Properties**.
 - c. On the **Certificates** tab, select your imported certificate.
 - d. On the **Flags** tab set **Force Encryption** to **Yes** and click **OK**.
 - e. Click **OK** on the Warning window.
 - f. Select **SQL Server Services**.
 - g. Right-click **SQL Server (MSSQLSERVER) > Restart** in the right pane.

Enabling NIST SP800-131A compliance on the controller

The IBM JRE for Windows operating system and Linux (Intel) operating systems is included with BigFix Remote Control and is installed when you install the controller software.

If you are using a Windows system, the JRE is included in the controller package `trc_controller_setup.exe` and `trc_controller.msi`. For Linux systems, the JRE is included in the package `ibm-trc-controller-jre-9.x.x.i386.rpm`. Where 9.x.x is the version that you want to install. The packages install the IBM Java Run-time Environment preconfigured with the IBM FIPS certified cryptographic provider and NIST SP800-131A enabled. The packages also register the MIME type `application/x-ibm-trc-jws` and a file association for `*.trcjws` files.

To check whether the controller is connected in FIPS or NIST SP800-131A mode during a remote control session, click **Controller tools > Show session information**. Encryption is set to AES FIPS when FIPS mode is enabled and is set to TLSv1.2 when NIST mode is enabled.

Enabling NIST SP800-131A compliance in the stand-alone controller

After you install the stand-alone controller, you can edit the properties file to enable NIST SP800-131A compliance.

If you install the controller component locally to start peer to peer remote control sessions, you must edit the `trc_controller.cfg` file to enable NIST SP800-131A compliance. To enable NIST SP800-131A compliance, complete the following steps.

1. Edit the `trc_controller.cfg` file on the system that the controller is installed on.

Windows systems

```
[controller install dir]\trc_controller.cfg
```

Where `[controller install dir]` is the installation directory you chose when you installed the controller.

Linux systems

```
opt/ibm/trc/controller/trc_controller.cfg
```

2. Set **sp800131a.compliance** to true.
3. Save the file.

Enable NIST SP800-131A compliance on the target

You can enable NIST SP800-131A compliance on the BigFix Remote Control target in various ways. NIST SP800-131A compliance can be enabled during installation when you are using the target installation

program. You can enable NIST SP800-131A compliance after the installation by editing the target registry on Windows systems, or by editing the configuration file on Linux systems.

Using the target user interface, choose the appropriate option to verify that NIST SP800-131A compliance is enabled on the target.

- On the BigFix Remote Control- Target user interface, click **Actions Menu > Connection info**.
- Hover the mouse over the **BigFix Remote Control** icon in the system notification area.

Enabling NIST SP800-131A compliance in a Windows target

When you are using a Windows operating system, you can enable NIST SP800-131A compliance on the target in two ways. You can enable compliance during installation or by editing the target registry after installation.

Enabling NIST SP800-131A compliance during the target installation

To enable the NIST SP800-131A compliance target property during installation, follow the instructions in [Install the target \(on page 57\)](#). On the **Server Address** screen of the target installer, click **Advanced settings**. Select **Enable NIST SP800-131A compliance (Enables FIPS)**.

Enabling NIST SP800-131A compliance during silent installation of the target

To enable NIST SP800-131A compliance during a silent installation of the target, you can use the **SP800131A** parameter in the installation command. For more information about a target silent installation, see [Running a target custom installation on a Windows system \(on page 85\)](#).

Use the following parameters to enable NIST SP800-131A compliance.

- TRC_SERVER_PROTOCOL=https
- TRC_SERVER_PORT=443
- SP800131A=yes

For example, `trc_target_setup.exe /s /v"/qn TRC_SERVER_HOSTNAME=yourserver TRC_SERVER_PROTOCOL=https TRC_SERVER_PORT=443 SP800131A=yes"`

Where *yourserver* is the host name or IP address of your BigFix Remote Control Server.

Enabling NIST SP800-131A compliance after target installation

After you install the BigFix Remote Control target, you can enable NIST SP800-131A compliance by editing the target registry. To enable NIST SP800-131A compliance, complete the following steps.

1. Run the `regedit` command at a command prompt window.
2. In the Windows registry, go to `HKEY_LOCAL_MACHINE\SOFTWARE\IBM\Tivoli\Remote Control\Target`
On a 64-bit system, the 32-bit registry keys are under the `WOW6432Node` key.
For example, `HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\IBM\Tivoli\Remote Control\Target`.
3. Right-click **SP800131ACompliance** and select **Modify**.
4. Type `yes` in the **Value data** field and click **OK**.
5. Restart the target service.
For more information about restarting the target service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Enabling NIST SP800-131A compliance on Linux or UNIX based targets

After you install the BigFix Remote Control target, you can enable NIST SP800-131A compliance by editing the `ibmtrct.conf` file. To enable NIST SP800-131A compliance, complete the following steps.

1. Edit the `/etc/ibmtrct.conf` file.
2. Set the value of `SP800131ACompliance` to `yes` and save the file.
3. Restart the target service.
For more information about restarting the target service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Enabling NIST SP800-131A compliance on the gateway

You can enable NIST SP800-131A compliance on the gateway component by editing the gateway configuration file that is created when you install gateway support.

The `trc_gateway.properties` file is in the following directory.

Windows systems

`\Documents and Settings\All Users\Application Data\IBM\Tivoli\Remote Control\Gateway`
or `\ProgramData\IBM\Tivoli\Remote Control\Gateway`.

Linux systems

`/etc`

To enable NIST SP800-131A compliance, complete the following steps.

1. Edit the `trc_gateway.properties` file.
2. Set **SP800131ACompliance = Yes**.
3. Save the file.
4. Restart the gateway service.

For more information about restarting the gateway service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Enabling NIST SP800-131A compliance on the broker

You can enable NIST SP800-131A compliance on the broker component by editing the broker configuration file that is created when you install broker support.

The `trc_broker.properties` file is in the following directory.

Windows systems

`\Documents and Settings\All Users\Application Data\IBM\Tivoli\Remote Control\broker`
or `\ProgramData\IBM\Tivoli\Remote Control\broker`.

Linux systems

`/etc`

To enable NIST SP800-131A compliance, complete the following steps.

1. Edit the `trc_broker.properties` file.
2. Set **SP800131ACompliance = Yes**.

3. Save the file.

4. Restart the broker service.

For more information about restarting the broker service, see [Manage the component services \(on page 127\)](#). Follow the steps in the section that is relevant to your operating system.

Enabling NIST SP800-131A compliance on the CLI tools

NIST SP800-131A compliance can be enabled during installation when you are installing the CLI tools on a Windows operating system. You can enable NIST SP800-131A after you install the CLI tools in Linux by editing the configuration file.

Enabling NIST SP800-131A compliance when you install the Windows cli tools

To enable NIST SP800-131A compliance during the installation of the command line interface tools, follow the instruction in [Installing the cli tools on a Windows system \(on page 103\)](#). Click **Advanced settings** on the **Server Address** screen, and select **Enable NIST SP800-131A compliance (Enables FIPS)** during the installation.

Enabling NIST SP800-131A compliance on the cli on Linux or UNIX based targets

After you install the cli tools, you can enable NIST SP800-131A compliance by editing the `ibmtrct.conf` file. To enable NIST SP800-131A compliance, complete the following steps.

1. Edit the `/etc/ibmtrct.conf` file.
2. Set the value of `SP800131ACompliance` to `yes`.
3. Save the file.

Chapter 13. Verifying the server installation

When you complete the server installation, you can verify it by completing the following steps:

1. In a browser window, type the address of the BigFix Remote Control server. For example, `http://yourservername/trc` where *yourservername* is the host name or IP address of your BigFix Remote Control server.
2. Verify that the BigFix Remote Control logon screen is displayed.
3. Log on with the following admin ID and password - *id=admin, password=password*.
4. At the change details screen, change the password by following the instructions that are given.

Chapter 14. Recover from installation errors

If you experience installation errors, use the following chapters to identify the problem and address it.

Recovery steps

Use the following information as a starting point to find log files and other information to help you recover from installation errors.

If you must contact HCL Software Support, gather the following information.

- If you are using a Windows operating system, any event log that is relevant to the installation error.
- The installation log files.
- Operating system version, including any service packs.
- The version of the WebSphere Application Server, database server, and Java.
- Hardware description.
- Installation media type.
- Windows services that were active during the unsuccessful installation. For example, antivirus software.

The following files can also be used to gather information about any errors that might occur.

`\tsetup.ini`

Contains some basic information, logged during an automated installation.

`[installdir]\install.log`

Contains internal debug messages.

`[installdir]\inst.ini`

Contains all parameters about the installation.

`[installdir]\wlp\usr\server\trcserver`

Contains configuration xml files.

`[installdir]\wlp\usr\server\trcserver\logs\messages.log`

`[installdir]\wlp\usr\server\trcserver\logs\messages_XXXXXXX.log`

`[installdir]\wlp\usr\server\trcserver\logs\ffdc directory`

Errors during installation

The following topics describe recovery actions for errors that might occur during the BigFix Remote Control server installation when you use the server installer program.

Not enough memory

Symptom

Memory error reported during the installation and the installation does not continue.

Cause

The memory check at the beginning of the installation determines that the computer that you are installing on does not have the required minimum memory for installation.

Solution

For more information about the requirements for memory, see [Server requirements \(on page 9\)](#).

DB2 connection error when database options are verified

Symptom

DB2 database connection error reported during installation.

Causes

During the installation if you select DB2 as the database, the installer verifies the information that is given in the database options screen. The user ID, password, and port values are used to establish a connection to the database. If a connection is not successful, an error is reported. This error also contains the error reported by DB2.

Solution

This error can be reported for any of the following reasons.

- Incorrect values are entered in the database options screen. Go back to the previous screen and verify the information.
- There is no database instance present. If you are planning to use DB2, it must be installed before the BigFix Remote Control server. A database instance must also be created.
- Cannot connect to the remote database. If you are using a remote database, verify that you can ping the IP address of the remote system.

Oracle pre-checks

Symptom

Oracle database connection error reported during installation.

Cause

During the installation if you select Oracle as the database, the installer verifies the information that is given in the database options screen by connecting to the database. If the connection fails, an error is reported. The error message contains the error that is returned from Oracle.

Solution

Go back to the previous screen and use the information that is given to correct the problem.

For example: If the Oracle database is not created before the installation, the following error is reported.

```
Failed to verify userid, password, server, database and driver
file combination supplied.Please verify details and try again.

( Listener refused the connection with the following error:
ORA-12505. TNS:listener does not currently know of SID given in
connect descriptor

The Connection descriptor used by the client was:
127.0.0.1:1521:TRCDB
```

In this case, you must cancel the installation and create the Oracle database before you install BigFix Remote Control again.

libstdc++.so.5 error when installing the server using the installation program

Symptoms

The server installation aborts with the following exception error in Linux.

```
This application has unexpectedly quit:Invocation of this Java application has caused
an InvocationTargetException. This application will now exit".
```

The installation log may show the following error

```
java.lang.unsignedshort :fontmanager (libstdc++.so.5: can not open shared
object file:No such file or directory)
```

Causes

Missing package required.

Solution

Install the **libstdc++.so.5** package. This can be installed by installing the **compat-libstdc++-33** package which includes libstdc++.so.5.

Errors after installation

When the installation of BigFix Remote Control is complete and the application service starts, you can log on. If you cannot log on successfully, use the following information to resolve the problem.

- Check that the server service is running.


Windows systems

In Windows services, check that the following service is started

BigFix Remote Control-Server.

Linux systems

The following service is created `/etc/init.d/trcserver` or `/etc/rc.d/init.d/trcserver` and started.

 **Note:** To manually stop or start the server type the following command.

```
/etc/init.d/trcserver [parameter] Where parameter is stop, start, or restart.
```

- Check the log files in the `[installdir]\wlp\usr\server\trcserver\logs` directory for any reported errors. You can also check the `trc.log` file in the server installation directory.
- If you are using an Oracle database, check that the user ASSET exists.

Out of memory error

Symptom

Out of memory errors are reported in the log files when the BigFix Remote Control Server is started. `Failed to instantiate heap` is reported in them.

Causes

There is not enough memory available to run the application. The reason for the error is that the maximum memory that is allocated to the heap is too high, and can be affected by other applications that are running or installed.

During installation, the installer attempts to set up the BigFix Remote Control application to use up to 70% of available RAM. The percentage is lowered if a Java virtual machine (JVM) cannot be started. However, if other software is installed, an out of memory error might also be reported in the BigFix Remote Control log files.


Solution

The solution to this problem is to use a supplied script to manually set the memory parameters to a lower value. This script, can be found in the BigFix Remote Control installation directory. Use the script to set the memory parameters and the number of threads and web connections.

- `tmem.cmd` - for Windows systems.
- `tmem.sh` - for UNIX based systems.


Run the following command from the BigFix Remote Control installation directory:

```
tmem.cmd minmem maxmem
```

 **Note:** Use `tmem.sh` for UNIX based systems.

minmem; maxmem

Sets the minimum and maximum memory to be allocated.

 **Note:** The 32-bit Java that is supplied in 32-bit eWAS can use a maximum of 2.7 GB only, no matter how much RAM is available.

You can also use the `tmem.cmd` and `tmem.sh` command to adjust the following parameters.

maxwebconn

Sets the number of web connections allowed. The default is 85 and can increase to 175.

maxthreads; minthreads

Sets the minimum and maximum threads allowed. Maximum threads are 50, increasing to 150.

To edit these parameters in version 9.x.x, complete the following steps:

1. Edit `trcsetup.cmd` or `trcsetup.sh`.

2. Edit the line that contains the call to the `memory.cmd` file. For example, `C:\TRC\server\tools\memory.cmd 163 49 135 1`

Where


- **maxwebconn** = parameter 1 (163)
- **minthreads** = parameter 2 (49)
- **maxthreads** = parameter 3 (135)

Do not edit parameter 4. Keep the value 1.

3. Change the required values.
4. Save the `trcsetup` file.
5. Type the following command.

```
trcsetup userid password certpassword
```

Where *userid* and *password* are the database connection credentials and *certpassword* is your certificate file password.

 **Note:** Derby does not have database credentials, therefore use user ID and password for the credentials. Type the following command when you are using Derby:

```
trcsetup userid password certpassword
```

Database connection authorization failure

Symptom

A database connection authorization failure error is reported in the log files.

Causes

The database password might be invalid.

Solution

Change the password by running the following command from the BigFix Remote Control installation directory:

Windows systems.

```
[installdir]\tools\tdbpasswd.cmd userid password. Where installdir is the BigFix Remote Control installation directory and userid and password are the database logon credentials.
```

UNIX based systems.

```
[installdir]/tools/tdbpasswd.sh userid password. Where installdir is the  
BigFix Remote Control installation directory and userid and password are the  
database logon credentials.
```

Run the command to change the database password for the application. Restart the BigFix Remote Control service after you run the command.

Application welcome page does not display

Symptom

The BigFix Remote Control server welcome page does not appear when you type in the BigFix Remote Control server URL in your browser.

Cause

The issue can occur for a number of reasons, which are reported in the log files.

Solution

Look through the `install.log` file in the server installation directory, for any reported errors.

DB2 connection error when database options are verified

Symptom

DB2 database connection error reported during installation.

Causes

During the installation if you select DB2 as the database, the installer verifies the information that is given in the database options screen. The user ID, password, and port values are used to establish a connection to the database. If a connection is not successful, an error is reported. This error also contains the error reported by DB2.

Solution

This error can be reported for any of the following reasons.

- Incorrect values are entered in the database options screen. Go back to the previous screen and verify the information.
- There is no database instance present. If you are planning to use DB2, it must be installed before the BigFix Remote Control server. A database instance must also be created.

- Cannot connect to the remote database. If you are using a remote database, verify that you can ping the IP address of the remote system.

Targets cannot contact the server

Symptom

Targets are not registering or updating their details on the BigFix Remote Control Server.

Causes

- The target does not have the correct URL for the server.
- The host name part of the URL, that is used to contact the server, does not match the common name in the server's SSL certificate.

Solution

When you install the target software the target contacts the server by using http or https, and the server URL that is defined during the installation of the target. However, there are two important things to note to ensure that the connection between the server and target is successful.

- The target must have the correct URL for the server.
- The host name part of the URL must match the common name in the server's SSL certificate.

When the BigFix Remote Control Server is installed with the installation program, you must ensure that you supply the correct values in the **Web server parameters** window. By default, the **upload data to server** field is populated with the computer name from the Windows operating system settings. The server installer program uses the field value to generate the server URL. The URL is then saved in the `trc.properties` file, in the **url** property and is also saved in the SSL certificate. Therefore, make sure that you specify the correct computer name during the installation. If you specify an incorrect value, the following problem might occur.

When a target contacts the server for the first time, it uses the **ServerURL** property from the target registry or configuration file to contact the server. When the server responds to the target, it includes the server address that is assigned to the **url** property in the `trc.properties` file. The target uses this URL to contact the server. If the address that is sent to the target is incorrect, the target can register once and then is not able to contact the server again. After a while, the target is marked as being offline. You are also unable to

start sessions with this target, because the target does not have a correct working URL with which to authenticate an incoming session.

The common name that is in the server's SSL certificate must be a host name that resolves to the IP address of the server. If the SSL certificate has, for example, *mytrcserver*, but on the target there is no way to translate *mytrcserver* to the IP address of the server, your environment is not correctly configured. The only names that are correctly supported are fully qualified domain names that are registered in the DNS. For example, *mytrcserver.example.ibm.com*. To use only *mytrcserver*, the server and target must be on the same local network and have WINS configured.

You can check that the DNS server is properly configured by using the `nslookup` command to query the full computer name and IP address.

For example: At a command prompt type, the following commands.

```
C:\>nslookup

Default Server:  dns.example.ibm.com
Address:  192.0.2.0

Type in the hostname of your server

> mytrcserver.example.ibm.com

Server:  dns.example.ibm.com
Address:  192.0.2.0

Name:    mytrcserver.example.ibm.com
Address:  192.0.2.1

Type in the ip address of your server

> 192.0.2.1

Server:  dns.example.ibm.com
Address:  192.0.2.0
```

```
Name:    mytrcserver.example.ibm.com
Address: 192.0.2.1
```

you can see that the server host name resolves to the correct IP address.

Errors when you use Oracle as the database

Symptom

`java.lang.ArrayIndexOutOfBoundsException` error reported when you use an Oracle database.


Cause

There is a problem with the Oracle jdbc drivers.

Solution

Choose the appropriate option to resolve the problem.

- Use the Oracle 10.2g JDBC 4 drivers. The drivers work with oracle 9, 10 and 11.
- If you are using the Oracle 11g drivers, manually edit the `trc.properties` file and set the following property **oracle.increment.keys.off=1**.

 **Note:** Restart the server service.

Errors when trying to connect to the Microsoft SQL database in FIPS compliancy mode

Symptom

Errors when trying to connect to the Microsoft SQL database in FIPS compliancy mode

Cause

Using the IBM JRE and the IBM JSSE provider and Websphere Application Server, which has been enabled for FIPS compliancy currently, does not work when using an MS SQL database.

Solution

These options only work with MS SQL when FIPS is **not** enabled in IBM Websphere.

Chapter 15. Uninstall the components

After you install the various BigFix Remote Control components, you can uninstall them in various ways.

Uninstall the server

To remove the BigFix Remote Control server, the method you choose depends on the type of installation that was run. If you installed the server by using the BigFix Remote Control installation program, you can uninstall the software by using the installer or by using Add or Remove programs. If you ran a manual installation of BigFix Remote Control Server, you must uninstall the software by using the IBM WebSphere Application Server administration console.

Uninstalling the server by using the installer

Use the following procedure to uninstall the BigFix Remote Control server software if you are using a Windows operating system or a Linux operating system.

To uninstall the BigFix Remote Control server by using the installer, complete the following steps :

1. Navigate to the BigFix Remote Control server installation directory.

The default directory or the specific directory that you chose when you installed the server. For example,

Windows systems

```
\Program Files\ibm\Tivoli\TRC\server
```

Linux systems

```
/opt/IBM/Tivoli/TRC/server
```

2. Double click **Uninstall BigFix Remote Control - Server.exe**
3. Click **Uninstall**.
4. Click **Done** when finished.

The BigFix Remote Control features, files, and folders that were created by the installer are removed.

Uninstalling the server application in IBM Websphere Application Server

If you have performed a manual installation of the BigFix Remote Control Server software, you can uninstall the software using the IBM Websphere Application Server administration console by completing the following steps:

To access the Administrative Console complete the following steps:

1. In your browser type

```
https://[server : port]/ibm/console
```

where *server* is the ipaddress or name for the application server machine for example localhost or 192.0.2.0 and *port* is the port that the server is listening on.

2. Logon with the ID and password that were defined when installing Websphere.
3. Expand Applications and click **Enterprise applications**.
4. Select the check box for the BigFix Remote Control server application.
5. Click **Uninstall**.
6. Select **Save** to save to the Master Configuration.

Uninstalling the server using Add or Remove programs

If you are using a Windows operating system you can uninstall the server software, using Add or Remove Programs by completing the following steps :

1. Open the **Control Panel**.
2. Double click **Add or Remove Programs**.
3. Select **BigFix Remote Control - Server**.
4. Click **Change Remove**.
5. Click **Uninstall**.
6. Click **Done** when finished.

Uninstalling the target on Windows systems

Using **Add or Remove Programs** to remove the target software from a Windows system.

To remove the target software by using Add or Remove Programs complete the following steps:

1. Open the **Control Panel**.
2. Double-click **Add or Remove Programs**.
3. Select **IBM BigFix Remote Control - Target**.
4. Click **Remove**.
5. Click **Yes** at the prompt.

The BigFix Remote Control target software is removed from your system.

Uninstalling the target on Linux systems

To remove the target software on Linux systems, complete the following steps:

1. To find the BigFix Remote Control package name that is installed, run the following command.

```
rpm -qa |grep trc
```

2. Run the following command:

```
rpm -e <trcpackage>
```

where *trcpackage* is your package name.

```
For example: rpm -e ibm-trc-target
```

You can verify that the target is removed by completing the following steps:

1. Run the command in step [1 \(on page 190\)](#) to make sure that there is no BigFix Remote Control package installed.
2. Run the following command to make sure that no BigFix Remote Control process is running.

```
ps -ef |grep trc
```

Chapter 16. Upgrade from previous versions

The following limitation is not an issue when you upgrade from version 9.0.0 or 9.0.1 or 9.1.0 to version 9.1.2.

In BigFix Remote Control version 9.0.0 new capabilities that were introduced can cause some compatibility issues with earlier versions if the different components are not upgraded in the correct order.

This limitation applies only to environments where the gateway and broker components are deployed. In these environments, the broker and gateway must be updated before the server or the target components. After they are upgraded, the targets and server can be upgraded in the order that best suits your environment, since there are no dependencies between them.

It is suggested to always back up any properties files as a precaution. However, for the controller upgrade in this release, you must back up the properties files as any existing properties are lost.

Upgrade the gateway component

You can upgrade the gateway component by using any of the following methods:

Using the installation files

For more information about obtaining the component installation files, see [Obtain the installation files \(on page 22\)](#). For more information about installing the gateway support on a Windows system, by using the installation files, see [Installing Windows gateway support \(on page 106\)](#). For more information about installing the gateway support in Linux, by using the installation files, see [Installing Linux gateway support \(on page 107\)](#).

Using the BigFix console

If you have the BigFix console infrastructure installed, you can use the update fixlet to upgrade the gateway support. For more information about the upgrade fixlet, see the *BigFix Remote Control Console User's Guide*.

Upgrade the broker component

You can upgrade the broker support by using any of the following methods:

Using the installation files

For more information about obtaining the component installation files, see [Obtain the installation files \(on page 22\)](#). For more information about installing the broker support on a Windows system, by using the installation files, see [Installing Windows broker support \(on page 108\)](#). For more information about installing the broker support in Linux, by using the installation files, see [Installing Linux broker support \(on page 109\)](#).

Using the BigFix console

If you have the BigFix console infrastructure installed, you can use the update fixlet to upgrade the broker support. For more information about the upgrade fixlet, see the *BigFix Remote Control Console User's Guide*.

Upgrade the server component

If you already installed the BigFix Remote Control Server software, you can upgrade the component by carrying out a similar installation type to your original installation.

Before you start the upgrade, you must back up your property files and any recording files if applicable. Back up any certificates, if applicable. For more information about backing up and restoring certificates, see the *BigFix Remote Control Administrator's Guide*

Property files

- `common.properties`
- `ldap.properties`
- `trc.properties`
- `log4j.properties`
- `controller.properties`

The files are in the following directories.

Windows systems

`[InstallDir]wlp\usr\servers\trcserver\apps\TRCAPP.ear\trc.war\WEB-INF\classes\` Where *InstallDir* is the BigFix Remote Control server installation directory. For example, `C:\Program Files (x86)\IBM\Tivoli\TRC\server\wlp\usr\servers\trcserver\apps\TRCAPP.ear\trc.war\WEB-INF\classes\`

Linux systems

`[InstallDir]wlp/usr/servers/trcserver/apps/TRCAPP.ear/trc.war/WEB-INF/classes/` Where *InstallDir* is the BigFix Remote Control server installation directory.


Recordings Files

The video recordings folder is defined by the **rc.recording.directory** property in the **trc.properties** file.

You can upgrade the server component by using any of the following methods:

Using the installation files


For more information about obtaining the component installation files, see [Obtain the installation files \(on page 22\)](#). For information about installing the server, by using the installer, see [Installing by using the server installer \(on page 32\)](#).

 **Note:** During the installation, select to keep existing property files and do not select to drop the database.

For information about installing the server, on WebSphere 8.5, see [Installing on WebSphere Application Server version 8.5: deploying the war file \(on page 44\)](#).

Using the BigFix console

If you have the BigFix console infrastructure installed, you can create and run a server installation task to upgrade the server. For more information about using the wizard to create a server configuration task, see the *BigFix Remote Control Console User's Guide*.

 **Note:** When you create the server task, do not select the drop database option if you want to keep your existing database.

When you complete the upgrade verify that the new version is installed, manually edit the new properties files. Update the values with the values that are in your backed up properties files. Restore your recording files and certificates if applicable

Upgrade the target component

You can upgrade the target component by using any of the following methods:

Using the installation files.

For more information about obtaining the component installation files, see [Obtain the installation files \(on page 22\)](#). For more information about installing the target component on a Windows system, by using the installation files, see [Installing the Windows target \(on page 57\)](#). For more information about installing the target component on a Linux system, by using the installation files, see [Installing the Linux target \(on page 81\)](#).

Using the BigFix console.

If you have the BigFix console infrastructure installed, you can use the update fixlet to upgrade the target component. For more information about the upgrade fixlet, see the *BigFix Remote Control Console User's Guide*.

Upgrade the controller component

The controller component upgrade is a major upgrade. Any existing properties are backed up and added to the new properties file.

If you are using a Linux operating system and are upgrading from Endpoint Manager for Remote Control version 9.0.1 or earlier, edit the `trc_controller.cfg.rpmnew` file. Compare the property values in the file with the values in the `trc_controller.cfg` file. Merge the differences into the `trc_controller.cfg` file and save the file.

Any of the following methods can be used to upgrade the controller component:

Using the installation files

For more information about obtaining the component installation files, see [Obtain the installation files \(on page 22\)](#). For more information about installing the controller component on a Windows system, by using the installation files, see [Installing the controller on a Windows system \(on page 96\)](#). For more information about installing the controller component in a Linux system, by using the installation files, see [Installing the Linux controller \(on page 96\)](#).

Using the BigFix console

If you have the BigFix console infrastructure installed, you can use the update fixlet to upgrade the controller component. For more information about using the update fixlet, see the *BigFix Remote Control Console User's Guide*.

Chapter 17. Maintaining the target installation

The BigFix Remote Control Target installation can be modified by using a maintenance program.

You can access the maintenance program on a system with Microsoft Windows by running the `trc_target_setup.exe` program. To access the maintenance program, complete the following steps:

1. Go to the target installation directory. For example,
`\Program Files\ibm\Tivoli Remote Control\RCTarget`
2. Double-click `trc_target_setup.exe`.
3. At the welcome screen click **Next**.
4. Select an option and click **Next**

Modify

Select this option to go through the target installation screens to modify the previously installed values.

To modify the installation properties, follow from step [5 \(on page 57\)](#).

Repair

Select this option to fix missing or corrupted files, shortcuts, and registry entries.

- a. Click **Repair**.
- b. Click **Finish**.

Remove

Select this option to remove the target software and all of its features.

- a. Click **Remove**.
- b. Click **Finish**.

Appendix A. Properties that can be set in the target configuration


You can configure target properties either during or after installation. The operating system on the target system determines which properties can be configured. The target properties determine the actions that can be carried out during a peer-to-peer session. If you set a server URL and set the **Managed** property to Yes, the actions are determined by the policies that are set on the Remote Control server.

For more information about which properties are configurable in each operating system, see [Table 24: Operating systems that the property is configurable in \(on page 219\)](#).

Windows systems

The target properties are saved in the target registry. Edit the target registry to modify the properties:

1. Edit the target registry and go to `HKEY_LOCAL_MACHINE\SOFTWARE\IBM\Tivoli\Remote Control\Target`

 **Note:** On a 64-bit system, all the 32-bit registry keys are under the **Wow6432Node** key. For example: `HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\IBM\Tivoli\Remote Control\Target`

2. Right-click the required property and select **Modify**
3. Set the required value and click **OK**.
4. Restart the target service.

Linux systems

The target properties are saved to the `/etc/ibmtrct.conf` file. Edit the file after installation to configure the target.

1. Edit the `ibmtrct.conf` file.
2. Modify the required properties.
3. Save the file.
4. Restart the target service.

macOS devices

You can configure the properties in the `trc_target.cfg` file when you install the target. For more information, see [Installing the BigFix Remote Control Target for macOS by using the .pkg file \(on page 83\)](#). The target properties are saved to `/Library/Preferences/`

`com.ibm.bigfix.remotecontrol.target.plist`. To modify a target property, complete the following steps:

1. Click **Go > Utilities > Terminal**.
2. Open the `Terminal.app`.
3. To modify a property, enter the following command.

```
sudo defaults write /Library/Preferences/com.ibm.bigfix.remotecontrol.target.plist
```

Keyword Value

Where **Keyword** is the property name and **Value** is the value for the property.

For example,


```
sudo defaults write /Library/Preferences/com.ibm.bigfix.remotecontrol.target.plist
```



```
LogLevel 4
```


4. Restart the target.
 - a. Click **Remote Control Target > Quit Remote Control Target**.
 - b. Open the `Remote Control Target.app`.



Target property definitions

Table 20. Installation option descriptions

Target property	Default Value	Description
ServerURL	Blank	For the target to register with the server and take part in remote control sessions that are started from the server, provide the BigFix Remote Control server URL in the format: <code>http://servername/trc</code> , where <i>servername</i> is the fully qualified name of your BigFix Remote Control server. For example, <code>http://trcserver.example.com/trc</code>  Note: If you provide a server URL and you want the target to take part only in remote control sessions that are started from the server, set AllowP2P to No.
ProxyURL	Blank	Host name or IP address for a proxy server, if you are using one.
BrokerList	Blank	The list of host names or IP addresses of the brokers and their ports, that you want the target to connect to. In the format, hostname1:port,hostname2:port,hostname3:port .

Target property	Default Value	Description
GroupLabel	Blank	<p>A target group name that the target is made a member of when the configuration is applied. This target group must exist in the BigFix Remote Control database.</p> <p> Note: The GroupLabel property can be used only if the target is not already registered with the server. If the target is already registered, it is not assigned to the target group. The allow.target.group.override property in the <code>trc.properties</code> file on the server must be set to Yes for the GroupLabel property value to be applied.</p>
PortToListen	888	Specify the TCP port that the target listens on. The default value for the BigFix Remote Control Target for macOS is 8787.
AllowP2P	Yes	<p>Used to enable peer-to-peer mode. Use this parameter to enable peer to peer connections regardless of the server status. Default value is No</p> <p>No</p> <p>A peer-to-peer session cannot be established between a controller and this target. If a ServerURL is provided, the targets can take part only in remote control sessions that are initiated from the server.</p> <p>Yes</p> <p>A peer-to-peer session can be established between a controller user and this target.</p> <p> Note: If this option is Yes and a server URL is provided, the target can take part in both peer-to-peer sessions and sessions that are initiated from the server.</p>
AllowP2PFailover	No	<p>Use this parameter to enable failover to peer-to-peer mode when the server is down or unreachable. AllowP2P must also be set to Yes. Default value is <i>No</i>.</p> <p>No</p> <p>The session does not failover to peer-to-peer mode when the server is down or unreachable.</p>

Target property	Default Value	Description
		<p>Yes</p> <p>The session does failover to peer-to-peer mode when the server is down or unreachable.</p>
FIPSCompliance	No	<p>Use this property to enable the use of a FIPS-certified cryptographic provider for all cryptographic functions. For more information about enabling FIPS compliance, see Federal information processing standard (FIPS 140-2) compliance in BigFix Remote Control (on page 150).</p> <p> Note: If you enable FIPS compliance on the target, you must also enable FIPS compliance on the controller components that are installed. Only the IBM Java Run-time Environment (JRE) is supported in FIPS-compliant mode and the JRE is installed when you install the controller software. To enable FIPS compliance on the controller, complete the following steps.</p> <ol style="list-style-type: none"> 1. Edit the <code>trc_controller.cfg</code> file on the system that the controller is installed on. <p>Windows systems</p> <pre>[controller installation dir]\trc_controller.cfg</pre> <p>where <code>[controller installation dir]</code> is the directory that the controller is installed in.</p> <p>Linux systems</p> <pre>opt/ibm/trc/controller/trc_controller.cfg</pre> 2. Set the fips.compliance property to Yes and save the file.
SP800131ACompliance	No	<p>Select this option to enforce NIST SP800-131A-compliant algorithms and key strengths for all cryptographic functions. For more information about enabling NIST SP800-131A compliance, see NIST SP800-131A compliance in BigFix Remote Control (on page 163).</p>

Target property	Default Value	Description
		<p> Note: If you enable NIST SP800-131A compliance on the target, you must also enable NIST SP800-131A compliance on the controller components that are installed. Only the IBM Java Run-time Environment (JRE) is supported in NIST SP800-131A compliant mode and the JRE is installed when you install the controller software. To enable NIST SP800-131A compliance on the controller, complete the following steps.</p> <ol style="list-style-type: none"> 1. Edit the <code>trc_controller.cfg</code> file on the system that the controller is installed on. <ul style="list-style-type: none"> Windows systems <pre>[controller installation dir]\trc_controller.cfg</pre> <p>where <i>[controller installation dir]</i> is the directory that the controller is installed in.</p> Linux systems <pre>opt/ibm/trc/controller/trc_controller.cfg</pre> 2. Set the sp800131A.compliance property to Yes and save the file.
Accessibility	No	Select this option to enable the accessibility UI. Available only on Windows operating system.
LogLevel	2	<p>0 - Logging is set to a minimal level.</p> <p>1 - Logging is set to ERROR level.</p> <p>2 - Logging is set to INFO level.</p> <p>4 - Logging is set to DEBUG level.</p> <p> Note: Use Log Level = 4 only by request from IBM. support.</p>
LogRollover	Daily	<p>Hourly</p> <p>Start a new log file on the hour. Recommended if the log is written to frequently or when you use a log level higher than 2.</p> <p>Daily</p>

Target property	Default Value	Description
		Start a new log file every day.
LogRotation	Weekly	<p>Daily</p> <p>Overwrite log files after 1 day. When LogRollover is set to Hourly, the suffix that is added to the log file name is 00H to 23H.</p> <p>Weekly</p> <p>Overwrite log files after 1 week. When LogRollover is set to Hourly, the suffix that is added to the log file name specifies the day and hour. Value can be Mon-00H to Sun-23H. When LogRollover is set to Daily, the suffix that is added to the log file name specifies the day. The value can be Mon to Sun.</p> <p>Monthly</p> <p>Overwrite log files after 1 month. 01-00H to 31-23H. When LogRollover is set to Hourly, the suffix that is added to the log file name specifies the numeric day of the month and the hour. Value can be 01-00H to 31-23H. When LogRollover is set to Daily, the suffix that is added to the log file name specifies the numeric day of the month. The value can be 01 - 31.</p> <p>Disabled</p> <p>LogRotation is disabled. When LogRollover is set to hourly, the suffix that is added to the log file name specifies the current date and time. Value can be YYYY-MM-DD-hh. When LogRollover is set to Daily, the suffix that is added to the log file name specifies the current date. The value can be YYYY-MM-DD.</p>

Table 21. Session option properties.


Target property	Default Value	Description
AllowMonitor	Yes	<p>Determines whether the target can take part in monitor peer-to-peer sessions. For information about the different types of remote control session that can be established, see <i>Types of remote control sessions that can be established</i> in the <i>BigFix Remote Control Controller User's Guide</i>.</p> <p>Yes</p> <p>The target can take part in monitor peer-to-peer sessions. The Monitor option is available for selection in the session type list in the controller window. The Open connection window also lists a Monitor option.</p> <p>No</p> <p>The target cannot take part in monitor peer-to-peer sessions. The Monitor option is not available in the session type list in the controller window.</p>
AllowGuidance	Yes	<p>Determines whether the target can take part in guidance peer-to-peer sessions.</p> <p>Yes</p> <p>The target can take part in guidance peer-to-peer sessions. The Guidance option is available in the session type list in the controller window. The Open connection window also lists a Guidance option.</p> <p>No</p> <p>The target cannot take part in guidance peer-to-peer sessions. The Guidance option is not available in the session type list in the controller window.</p>
AllowActive	Yes	<p>Determines whether the target can take part in active peer-to-peer sessions.</p> <p>Yes</p>

Target property	Default Value	Description
		<p>The target can take part in active peer-to-peer sessions. The Active option is available in the session type list in the controller window. The Open connection window also contains an Active option.</p> <p>No</p> <p>The target cannot take part in active peer-to-peer sessions. The Active option is not available in the session type list in the controller window.</p>
DisableChat	No	<p>Determines the ability to start a chat session with the target and also chat to the controller user during a peer-to-peer session.</p> <p>Yes</p> <p>If Chat Only is chosen as the connection type on the open connection screen, the session is refused. During the session, the chat icon is not available in the controller window.</p> <p>No</p> <p>A Chat Only session can be initiated from the open connection window. During the session, the chat icon is available in the controller window.</p>
DisableFilePull	No	<p>Determines the ability to transfer files from the target to the controller during the session.</p> <p>Yes</p> <p>Files cannot be transferred from the target to the controller.</p> <p>No</p> <p>Files can be transferred from the target to the controller.</p>
DisableFilePush	No	<p>Determines the ability to transfer files from the controller to the target during the session.</p> <p>Yes</p> <p>Files cannot be transferred from the controller to the target.</p>

Target property	Default Value	Description
		<p>No</p> <p>Files can be transferred from the controller to the target.</p>
DisableClipboard	No	<p>Determines the availability of the clipboard transfer menu in the controller UI in a peer-to-peer session. Use the menu to transfer the clipboard content between the controller and target during a remote control session.</p> <p>Yes</p> <p>The clipboard transfer menu is not available during the session to transfer the clipboard content to and from the target.</p> <p>No</p> <p>The clipboard transfer menu is available during the session.</p>
AllowRecording	Yes	<p>The controller user can make and save a local recording of the session in the controlling system.</p> <p>Yes</p> <p>The record option is available in the controller window.</p> <p>No</p> <p>The record option is not available in the controller window.</p>
AllowCollaboration	Yes	<p>Use this property to allow more than one controller to join a session. Determines the availability of the collaboration icon on the controller window.</p> <p>Yes</p> <p>The collaboration icon is available in the controller window.</p> <p>No</p> <p>The collaboration icon is not available in the controller window.</p>

Target property	Default Value	Description
AllowHandover	Yes	<p>The master controller in a collaboration session, can hand over control of the session to a new controller. Determines the availability of the Handover button on the collaboration control panel.</p> <p>Yes</p> <p>The Handover button is displayed in the collaboration control panel.</p> <p>No</p> <p>The Handover button is not displayed in the collaboration control panel.</p>
AllowForceDisconnect	No	<p>Determines whether a Disconnect session button is available in the message window that is displayed when you attempt to connect to the target. You can use the Disconnect session option to disconnect the current session.</p> <p>Yes</p> <p>The disconnect button is displayed in the message window.</p> <p>No</p> <p>The disconnect button is not displayed in the message window.</p>
ForceDisconnectTimeout	45	<p>Number of seconds you must wait for the controller user to respond to the prompt to disconnect the current session. If they do not respond in the time that is given, they are automatically disconnected from the session. The timer takes effect only when AllowForceDisconnect and CheckUserLogin are set to Yes. The default value is 45.</p>
AutoWinLogon	Yes	<p>Determines whether a session can be started when no users are logged on at the target. Determines whether the user acceptance window is displayed on a target where the target user is not logged on.</p> <p>Yes</p> <p>Session is started with the target.</p>

Target property	Default Value	Description
		<p>The acceptance window is not visible on the target and the session is established.</p> <p>No</p> <p>Session is not started and the following message is displayed. Session rejected because there is no user logged to confirm the session. The session is refused because no user is logged on at the target to accept the session.</p>
RunPreScript	No	<p>Determines whether a user-defined script is run before the remote control session starts. The script is run just after the session is allowed but before the controller user has access to the target. The outcome of running the script and the continuation of the session is determined by the value that is set for Proceed on pre/post-script failure.</p> <p>Yes</p> <p>When a remote control session is requested, the defined script is run before the controller user has access to the target.</p> <p>No</p> <p>No script is run before the session.</p> <p>For more information about setting up pre and post session scripts, see the <i>BigFix Remote Control Administrator's Guide</i>.</p>
RunPostScript	No	<p>Determines whether a user-defined script is run after the remote control session finishes.</p> <p>Yes</p> <p>When a remote control session ends, the user-defined script is run.</p> <p>No</p> <p>No script is run after the session.</p> <p>For more information about setting up pre and post session scripts, see the <i>BigFix Remote Control Administrator's Guide</i>.</p>

Target property	Default Value	Description
ProceedOnScriptFail	No	<p>The action to take if the pre-script or post-script execution fails. A positive value or 0 is considered a successful run of the pre-script or post-session script. A negative value, a script that is not found, or not finished running within 3 minutes is considered a failure.</p> <p>Yes</p> <p>If the pre-script or post-script run fails, the session continues.</p> <p>No</p> <p>If the pre-script or post-script run fails, the session does not continue and ends.</p>
WorkaroundW2K3RDP	No	<p>Automatically reset the console after a Remote Desktop console session. When a Remote Desktop user uses the /admin or /console option to start a Remote Desktop session with a Windows Server 2003 system and a user starts a remote control session with this target before, during or after the Remote Desktop session, remote control is unable to capture the display. The result is that a gray screen is shown in the controller. This issue is a limitation in Windows Server 2003 operating systems. Therefore, this property introduces a workaround that will reset the Windows session either after each Remote Desktop session ends, or before a remote control session starts, depending on the value Yes.</p> <p>0</p> <p>The workaround is disabled. This value is the default value.</p> <p>1</p> <p>Reset the session automatically when a remote control session is started.</p> <p> Note: The Windows session takes a couple of minutes to initialize and a blank desktop is displayed on the controller until the initialization is complete. A message informs the controller user</p>

Target property	Default Value	Description
		<p>that the session is being reset and it might take a few minutes.</p> <p>2</p> <p>Reset the session automatically when the Remote Desktop user logs out.</p>
EnableTrueColor	No	<p>Determines whether the target desktop is displayed in high-quality colors in the controller window at the start of a session. Used together with Lock color quality.</p> <p>Yes.</p> <p>The target desktop is displayed in true color 24-bit mode at the start of the session. Partial screen updates are also enabled.</p> <p>No.</p> <p>The target desktop is displayed in 8-bit color mode at the start of the session. Partial screen updates are also enabled. This value is the default value.</p>
LockColorDepth	No	<p>Determines whether the color quality that a remote control session is started with can be changed during the session. Used together with Enable high quality colors.</p> <p>Yes.</p> <p>The initial color quality, for the remote control session, is locked and cannot be changed during the session. The Performance settings icon is disabled in the controller window. The controller user cannot change settings to improve the session performance if their network is slow.</p> <p>No.</p> <p>The color quality can be changed during the session. The Performance settings icon is enabled in the controller window.</p>



Target property	Default Value	Description
RemoveBackground	No	<p>If a desktop background image is set on the target, this property can be used to remove the background from view during a remote control session.</p> <p>Yes.</p> <p>The desktop background image on the target is not visible during a remote control session.</p> <p>No.</p> <p>The desktop background image on the target is visible during a remote control session.</p>
NoScreenSaver	No	<p>Stops the target from sending screen updates when it detects that the screen saver is active.</p> <p>Yes.</p> <p>While the screen saver is active on the target system, the target stops transmitting screen updates. The controller displays a simulated screen saver so that the controller user is aware that a screen saver is active on the remote display. The controller user can remove the screen saver by pressing a key or moving the mouse.</p> <p>No.</p> <p>A simulated screen saver is not displayed in the session window. The target screen is displayed as normal and the target continues to transmit screen updates.</p>
Managed	Yes	<p>Determines whether the target registers with the Remote Control server.</p> <p>Yes.</p> <p>The target registers with the Remote Control server and periodically contacts the server.</p> <p>No.</p>

Target property	Default Value	Description
		The target does not register with the Remote Control server. The target can take part only in peer-to-peer sessions.

Table 22. User acceptance property descriptions

Target property	Default Value	Description
ConfirmTakeOver	Yes	<p>Determines whether the acceptance window is displayed on the target, when a remote control session is requested.</p> <p>Yes</p> <p>The user acceptance window is displayed and the target user can accept or refuse the session.</p> <p>No</p> <p>The user acceptance window is not displayed and the session is established.</p>
ConfirmModeChange	Yes	<p>Determines whether the user acceptance window is displayed when the controller user selects a different session mode from the session mode list on the controller window.</p> <p>Yes</p> <p>The user acceptance window is displayed each time a session mode change is requested and the target user must accept or refuse the request.</p> <p>No</p> <p>The user acceptance window is not displayed and the session mode is changed automatically.</p>
ConfirmFileTransfer	Yes	<p>Determines whether the user acceptance window is displayed when the controller user selects to transfer files between the target and the controller.</p> <p>Yes</p> <p>The acceptance window is displayed in the following two cases. The target user must accept or refuse the file transfer.</p>


Target property	Default Value	Description
		<ul style="list-style-type: none"> • The controller user selects pull file from the file transfer menu on the controller window. The target user must select the file that is to be transferred after they accept the request. • The controller user selects send file to controller from the Actions menu in the target window. <p>No</p> <p>The acceptance window is not displayed and files are transferred automatically from the target to the controller system when requested.</p>
ConfirmSysInfo	Yes	<p>Determines whether the user acceptance window is displayed when the controller user requests to view the target system information.</p> <p>Yes</p> <p>When the controller user clicks System information in the controller window, the user acceptance window is displayed. The target user must accept or refuse the request. If the target user clicks accept, the target system information is displayed in a separate window on the controller system. If they click refuse, a message is displayed on the controller and the system information is not displayed.</p> <p>No</p> <p>The target system information is displayed automatically when the controller user clicks the system information icon.</p>
ConfirmRecording	Yes	<p>Determines whether the user acceptance window is displayed when the controller user clicks the record icon on the controller window.</p> <p>Yes</p> <p>When the controller user clicks the record icon on the controller window, a message window is displayed. If the target user clicks Accept, the controller user can select a directory to save the recording to. If the target user clicks Refuse, a recording refused message is displayed to the controller.</p>

Target property	Default Value	Description
		<p> Note: After the target user accepts the request for recording, if the controller user stops and restarts local recording, the acceptance window is not displayed.</p> <p>No</p> <p>When the controller user clicks the record icon on the controller window, the message window is not displayed. The controller user can select a directory to save the recording to.</p>
ConfirmCollaboration	Yes	<p>Determines whether the user acceptance window is displayed when another controller user requests to join a collaboration session with a target.</p> <p>Yes</p> <p>When the controller user tries to join the collaboration session, the user acceptance window is displayed. The target user must accept or refuse the request to allow the additional controller to join the session. If the target user clicks accept, the additional controller joins the collaboration session. If they click refuse, a message is displayed on the controller system and the additional controller cannot join the collaboration session.</p> <p>No</p> <p>The additional controller automatically joins the collaboration session when they try to connect to the master controller of the session.</p>
AcceptanceGraceTime	45	<p>Sets the number of seconds to wait for the target user to respond before a session starts or times out, used with Confirm incoming connections.</p> <ul style="list-style-type: none"> • Acceptable values 0 - 60. If set to 0, the target user is not asked to respond to the session request. <p> Note: If Confirm incoming connections is Yes, Acceptance grace time must be set to a value >0 to provide the target user with enough time to respond.</p>


Target property	Default Value	Description
AcceptanceProceed	No	<p>The action to take if the user acceptance window timeout lapses. The target user did not click accept or refuse within the number of seconds defined for Acceptance grace time.</p> <p>Yes</p> <p>Session is established.</p> <p>No</p> <p>Session is not established.</p>
HideWindows	No	<p>Determines whether the Hide windows check box is displayed on the user acceptance window when Confirm incoming connections is also set to Yes.</p> <p>Yes</p> <p>The Hide windows check box is displayed on the user acceptance window.</p> <p>No</p> <p>The Hide windows check box is not visible on the user acceptance window.</p>


Table 23. Security property descriptions


Target property	Default Value	Description
CheckUserLogin	Yes	<p>Determines whether a logon window is displayed when the controller user clicks a session type button on the Open Connection window.</p> <p>Yes</p> <p>The logon window is displayed and the controller user must log on with a valid Windows operating system ID and password. If the logon credentials are invalid, the target refuses the session.</p> <p>No</p> <p>The logon window is not displayed and the session is established.</p>
CheckUserGroup	see description	Default value.



Target property	Default Value	Description
		<p>Windows systems</p> <pre>BUILTIN\Administrators</pre> <p>Linux systems</p> <pre>wheel</pre> <p>When CheckUserGroup has a value set, the user name that is used for authentication must be a member of one of the groups that are listed. If the user is not a member, the session is refused. Multiple groups must be separated with a semicolon. For example, <code>wheel;trcusers</code></p> <p> Note: By default, on Windows systems, only the Administrator user is granted access. On Linux systems, by default no users are granted access. To resolve this issue, complete one of the following steps.</p> <ol style="list-style-type: none"> 1. To also grant administrator rights to the users, make them members of the Administrators group on Windows systems or the wheel group on Linux systems. 2. For users with no administrator rights, complete the following steps. <ol style="list-style-type: none"> a. Create a group or use an existing group. For example, the following command can be run as root: <pre>groupadd trcusers</pre> b. Add the users to this group. For example, the following command can be run as root to add bsmith to trcusers: <pre>usermod -a -G trcusers <bsmith></pre> c. Add the group to the list in the Authorized user group field.
AuditToSystem	Yes	<p>Determines whether the actions that are carried out during remote control sessions are logged to the application event log on the target. This file can be used for audit purposes.</p> <p>Yes</p>

Target property	Default Value	Description
		<p>Entries that correspond to each action that is carried out during the session, are logged in the application event log of the target.</p> <p>No</p> <p>No entries are logged to the application event log.</p>
AutoSaveChat	No	<p>Determines whether the chat text, entered during a chat session, can be saved.</p> <p>Yes</p> <p>The chat text is saved as an html file. The file is <code>chat-username-date.html</code>, where <i>username</i> is the display name of the logged on user on the controller machine in a peer-to-peer session. In managed mode <i>username</i> is the display name for the controller user that is on the server. The date is in the format <code>YYYYMMDD</code>. The file is saved in the working directory of the target. The location of the working directory is defined by the target property WorkingDir. For example, on Windows systems, the file is saved to</p> <pre>c:\ProgramData\IBM\Tivoli\Remote Control.</pre> <p>On Linux systems the file is saved to <code>/var/opt/ibm/trc/target/</code>.</p> <pre>c:\Documents and Settings\All Users \Application Data\IBM\Tivoli\Remote Control</pre> <p>No</p> <p>The chat text is not saved to a file.</p>
EnableFileTransferSystemAccess	No	<p>Determines whether the file transfer session allows for target file system access using System privileges (Windows) or root privileges (Linux). This option is valid for peer to peer sessions only.</p> <p>Yes</p>

Target property	Default Value	Description
		<p>The file transfer session uses System privileges (Windows) or root privileges (Linux) on the target file system.</p> <p>No</p> <p>The file transfer session uses the privileges of the logged on user on the target file system.</p> <p> Note: If the option is set to No, and there is no logged on user on the target during the file transfer session, an error message is displayed.</p>
SessionDisconnect	No	<p>Determines whether the target computer is automatically locked when the remote control session ends. Allowed value: <i>lock</i>.</p> <p>When you set the value to <i>lock</i>, the target computer is automatically locked at the end of the session. If the property is blank or set to another value, the target computer is not automatically locked at the end of the session.</p> <p>Yes</p> <p>The target computer is automatically locked at the end of the session.</p> <p>No</p> <p>The target computer is not automatically locked at the end of the session.</p>
AllowPrivacy	Yes	<p>Determines whether a controller user can lock the local input and screen of the target in a remote control session. Determines the visibility of the Enable Privacy option on the controller window.</p> <p>Yes</p> <p>The Enable Privacy option is available in the Perform Action in target menu in the controller window.</p> <p>No</p>

Target property	Default Value	Description
		<p>The Enable Privacy option is not available in the Perform Action in target menu in the controller window.</p>
AllowInputLock	Yes	<p>This property works with Allow privacy and on its own. You can use Allow input lock to lock the target users mouse and keyboard during a remote control session.</p> <p>Yes</p> <p>The lock target input menu item is enabled, in the Perform action in target menu in the controller window. Select lock target input to lock the target users mouse and keyboard during a remote control session. The target screen is still visible to the target user.</p> <p>No</p> <p>The lock target input menu item is not enabled in the Perform action in target menu in the controller window.</p> <p> Note: If the option to Enable Privacy is Yes during a session, the remote user input is automatically locked. It is not possible to enable privacy without also locking the input.</p>
EnablePrivacy	No	<p>Determines whether the local input and screen are locked for all sessions. Therefore, the target user cannot input or do anything on the target while in a remote control session.</p> <p>Yes</p> <p>The target screen is blanked out by the privacy bitmap when the session starts, preventing the target user from interacting with the screen while in the session. The target desktop is still visible to the controller user in the controller window.</p> <p>No</p> <p>The target screen is not blanked out when the session is started and the target user can interact with the screen.</p>

Target property	Default Value	Description
EnableInputLock	No	<p>This property works with Enable privacy. When privacy mode is enabled, use Enable input lock to determine whether the target user can view their screen, during a remote control session.</p> <p>Yes</p> <p>The target screen is visible to the target user during the session, while in privacy mode but the mouse and keyboard control is locked.</p> <p>No</p> <p>The target screen is not visible to the target user. The privacy bitmap is displayed on the target during the session. The target users mouse and keyboard input is also disabled.</p> <p> Note: Enable privacy must be Yes for Enable input lock to take effect.</p>
DisablePanicKey	No	<p>Determines whether the Pause Break key can be used by the target user to automatically end the remote control session.</p> <p>Yes</p> <p>The target user cannot use the Pause Break key to automatically end the remote control session.</p> <p>No</p> <p>The target user can use the Pause Break key to automatically end the remote control session.</p>
EnableOSSN	No	<p>Determines whether a semi-transparent overlay is displayed on the target computer to indicate that a remote control session is in progress. Use this property when privacy is a concern so that the user is clearly notified when somebody can remotely view or control their computer.</p> <p>Yes</p> <p>The semi-transparent overlay is displayed on the target screen with the text BigFix Remote Control and what type of remote control session is in progress. For example, <i>BigFix Remote Control -</i></p>

Target property	Default Value	Description
		<p><i>Active Mode</i>. The overlay does not intercept keyboard or mouse actions. The user is still able to interact with their screen.</p> <p>No</p> <p>No overlay is displayed on the target computer.</p> <p> Note: This policy is only supported on targets where a Windows operating system is installed.</p>
DisableGUI	No	<p>Determines whether the target UI is visible when the remote control session is starting and also during the session.</p> <p> Note: This option works only when the target is installed in peer-to-peer mode and the Managed target property is set to No. This option is ignored when applied to any targets that were installed by using the BigFix Remote Control server mode when a server URL was supplied.</p> <p>Yes</p> <p>The target UI is not visible on the target and the target user is not aware that the session is started. The BigFix Remote Control target icon is not visible in the Windows system tray.</p> <p>No</p> <p>The target UI is displayed on the target as the session is starting and is available to the target user during the remote control session.</p>

Operating systems that the property is configurable in

Table 24. Operating systems that the property is configurable in

Property name	Windows	Linux	macOS - available from V9.1.4
ServerURL	*	*	
ProxyURL	*	*	
BrokerList	*	*	*

Property name	Windows	Linux	macOS - available from V9.1.4
GroupLabel	*	*	
PortToListen	*	*	*
AllowP2P	*	*	
AllowP2PFailover	*	*	
FIPSCompliance	*	*	
SP800131ACompliance	*	*	
Accessibility	*		
LogLevel	*	*	*
LogRollover	*	*	*
LogRotation	*	*	*
AllowMonitor	*	*	*
AllowGuidance	*	*	
AllowActive	*	*	*
DisableChat	*	*	
DisableFilePull	*	*	*
DisableFilePush	*	*	*
DisableClipboard	*	*	
AllowRecording	*	*	*
AllowCollaboration	*	*	*
AllowHandover	*	*	*
AllowForceDisconnect	*	*	
ForceDisconnectTimeout	*	*	
AutoWinLogon	*	*	
RunPreScript	*	*	
RunPostScript	*	*	

Property name	Windows	Linux	macOS - available from V9.1.4
ProceedOnScriptFail	*	*	
WorkaroundW2K3RDP	*		
EnableTrueColor	*	*	*
LockColorDepth	*	*	*
RemoveBackground	*		
NoScreenSaver	*		
Managed	*	*	
ConfirmTakeOver	*	*	*
ConfirmModeChange	*	*	*
ConfirmFileTransfer	*	*	*
ConfirmSysInfo	*	*	*
ConfirmRecording	*	*	*
ConfirmCollaboration	*	*	*
AcceptanceGraceTime	*	*	*
AcceptanceProceed	*	*	*
HideWindows	*	*	
CheckUserLogin	*	*	
CheckUserGroup	*	*	
AuditToSystem	*	*	*
AutoSaveChat	*	*	
EnableFileTransferSystemAccess	*	*	
SessionDisconnect	*	*	
AllowPrivacy	*		
AllowInputLock	*		
EnablePrivacy	*		

Property name	Windows	Linux	macOS - available from V9.1.4
EnableInputLock	*		
DisablePanicKey	*		
EnableOSSN	*		
DisableGUI	*		

Appendix B. Support

For more information about this product, see the following resources:

- [Knowledge Center](#)
- [BigFix Support Center](#)
- [BigFix Support Portal](#)
- [BigFix Developer](#)
- [BigFix Wiki](#)
- [HCL BigFix Forum](#)

Notices

This information was developed for products and services offered in the US.

HCL may not offer the products, services, or features discussed in this document in other countries. Consult your local HCL representative for information on the products and services currently available in your area. Any reference to an HCL product, program, or service is not intended to state or imply that only that HCL product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any HCL intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-HCL product, program, or service.

HCL may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

HCL
330 Potrero Ave.
Sunnyvale, CA 94085
USA
Attention: Office of the General Counsel

For license inquiries regarding double-byte character set (DBCS) information, contact the HCL Intellectual Property Department in your country or send inquiries, in writing, to:

HCL
330 Potrero Ave.
Sunnyvale, CA 94085
USA
Attention: Office of the General Counsel

HCL TECHNOLOGIES LTD. PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. HCL may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-HCL websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this HCL product and use of those websites is at your own risk.

HCL may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

HCL

330 Potrero Ave.

Sunnyvale, CA 94085

USA

Attention: Office of the General Counsel

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by HCL under terms of the HCL Customer Agreement, HCL International Program License Agreement or any equivalent agreement between us.

The performance data discussed herein is presented as derived under specific operating conditions. Actual results may vary.

Information concerning non-HCL products was obtained from the suppliers of those products, their published announcements or other publicly available sources. HCL has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-HCL products. Questions on the capabilities of non-HCL products should be addressed to the suppliers of those products.

Statements regarding HCL's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs

in any form without payment to HCL, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. HCL, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS," without warranty of any kind. HCL shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year).

Portions of this code are derived from HCL Ltd. Sample Programs.

Trademarks

HCL Technologies Ltd. and HCL Technologies Ltd. logo, and hcl.com are trademarks or registered trademarks of HCL Technologies Ltd., registered in many jurisdictions worldwide.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other product and service names might be trademarks of HCL or other companies.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the HCL website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of HCL.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of HCL.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

HCL reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by HCL, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

HCL MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

Index

A

add a token for secure target registration

115

application

deployment

55

application server setup

DB2

45

mssql

52

oracle

49

B

broker

upgrading

191

broker requirements

19

broker support

installing

108

C

command line tools

installing

linux

105

windows

103

command-line tools

installing

103

components

installing

22

configuration

server

enabling email

129

controller

for mac

fixlet

97

pkg file

98

installation

supported operating systems

99

installing

95

linux

96

Windows

96

pre-configuring

99

upgrading

194

controller requirements

16

custom install

target

84

D

data import

LDAP

130

data source

DB2

creating

47

MSSQL

creating	server
54	11
Oracle	F
creating	FIPS compliance
50	150
database	at target installation
mssql	159
creating	linux target
31	enabling
mssql database	160
permissions	server
31	enabling
database authentication data	153
DB2	target
45	after installation
MSSQL	160
52	target silent install
Oracle	159
49	FIPS compliancy
database setup	controller
DB2	enabling
25	156
oracle	enabling on server
27	automated server installation
default installation	154
server	manual server installation
32	153
deploying the war file	target
44	enabling
E	159
email	windows target
enabling	enabling
129	159
Enabling SP800-131A compliance on the CLI	G
tools	gateway
176	upgrading
environment guidelines	191

gateway support	184
installing	recovering
106	178
linux	installation files
107	extracting to disk
silent install	111, 112
107	obtaining
windows	22
106	installing
getting started	controller
21	95
I	target
installation	57
basic setup	target rpm file
6	81
firewall traversal	target spb file
8	95
verifying	Installing
177	server
installation errors	25
DB2	installing a pre-configured controller component
179, 184	99
during installation	installing broker support
178	108
linux libstdc++.so.5 package	Linux
180	109
not enough memory	Windows
179	108
oracle	installing gateway support
180	106
post installation	installing linux gateway support
181	107
DB2 authentication failure	installing the command-line tools
183	103
out of memory	Installing the components
181	22
welcome page not appearing	installing the Linux controller

- 96
- Installing the Windows controller
 - 96
- Installing the Windows target
 - 57
- installing Windows gateway support
 - 106
- J**
- jdbc provider
 - MSSQL
 - creating
 - 53
 - Oracle
 - creating
 - 49
- L**
- LDAP
 - configuration file
 - 145
 - configuring
 - 130
 - connection credentials
 - 133
 - connection security
 - parameters
 - 135
 - enabling
 - 143
 - errors
 - 143
 - groups
 - importing
 - 141
 - ldap.security_authentication
 - 135
 - SASL secure connection
 - 136
 - SSL secure connection
 - 137
 - synchronization
 - 130
 - user authentication
 - 137, 137
 - user search
 - 139
 - verify imported groups
 - 145
 - verifying a connection
 - 132
- linux components
 - restarting
 - 127
 - starting
 - 127
 - stopping
 - 127
- log files
 - location
 - 178
- M**
- mac controller
 - fixlet
 - 97
 - installation
 - 97, 97, 98
 - pkg file
 - 98
- mac target
 - deployment
 - fixlet
 - 82
 - installation
 - 82, 83
 - pkg file

- 83
- managing the component services
 - 127
- manual install
 - application deployment
 - 55
 - application server setup
 - 44
 - database setup
 - 25
- MSSQL
 - FIPS compliancy
 - connection errors
 - 187
 - mssql database
 - creating
 - 31
- N**
 - NIST compliance
 - 163
 - broker
 - enabling
 - 175
 - cli
 - enabling
 - 176
 - enabling
 - automated server installation
 - 165
 - manual server installation
 - 164
 - gateway
 - enabling
 - 174
 - linux target
 - enabling
 - 174
 - server
 - enabling
 - 164
 - target
 - enabling
 - 172
 - using the server installer
 - 164
 - O**
 - Obtaining the installation files
 - 22
 - operating requirements
 - 6
 - oracle database
 - out of bounds errors
 - 187
 - Oracle database
 - creating
 - 27
 - setting permissions
 - 28
 - Overview
 - 3
 - P**
 - platform support
 - broker
 - 19
 - controller
 - 16
 - server
 - 9
 - target
 - 16
 - R**
 - registration token
 - add after target installation
 - 118

- Linux target
 - adding
 - 119
- silent installation option
 - 117
- target installer option
 - 117
- target upgrade
 - 119
- Windows target
 - adding
 - 117
- requirements
 - 6
- RPM build tree
 - configuring
 - 92
- RPM package
 - building
 - 95
- RPM source file
 - installing
 - 93
 - obtaining
 - 93
- S**
 - secure target registration
 - enabling
 - 114
 - rc.enforce.secure.registration
 - 115
 - server
 - 114
 - server installer
 - 114
 - server environment guidelines
 - 11
 - large environment
 - 14
 - medium environment
 - 13
 - small environment
 - 12
 - server installation
 - BigFix
 - console
 - 57
 - installer
 - 32
 - war file
 - 44
 - server installation types
 - 11
 - server requirements
 - 9
 - Setting up LDAP synchronization
 - 130
 - smart card
 - driver installation
 - 121
 - target installer option
 - 121
 - smart card reader driver
 - add by using the installer
 - 122
 - Fixlet installation
 - 124
 - remove by using the installer
 - 122
 - silent installation
 - 123
 - target upgrade
 - 123
 - smartcard

certificate	target
installation Fixlet	after installation
125	173
certificates	enabling
downloading	172
125	target silent installation
SP800-131A compliance	173
163	using the server installer
broker	164
enabling	using the target installer
175	173
cli	windows target
enabling	enabling
176	173
linux	SPEC file
176	customizing
windows	93
176	system requirements
controller	broker
enabling	19
171	controller
stand-alone	16
172	gateway
enabling	18
automated server installation	server
165	9
manual server installation	target
164	16
gateway	T
enabling	target
174	for mac
linux target	pkg file
enabling	83
174	installing
server	Windows
enabling	57
164	modifying

Windows	122
195	target properties
smart card driver	configuring
121	196
smart card installer option	definitions
121	196
smart card silent installer option	target requirements
123	16
uninstalling	target silent installer
Linux	registration token option
190	117
Windows	targets
189	not registering
upgrading	185
193	targets
target config file	not visible on server
customising	185
94	troubleshooting
target install	installation errors
custom install	178
RPM for Linux	U
92	uninstalling
windows	188
85	server
target installation	188
rpm file	in WAS
81	188
spb file	using add remove programs
95	189
target installer	using installer
add registration token	188
118	upgrading
add smart card reader driver	controller
122	194
registration token option	server
117	192
remove smart card reader driver	target

- 193
- upgrading from previous versions
 - 191
- upgrading the broker
 - 191
- upgrading the gateway
 - 191
- using this guide
 - 5

W

- war file deployment
 - database setup
 - 25
- websphere variables
 - db2
 - verifying
 - 46
 - oracle
 - verifying
 - 50
 - verifying
 - 53
- windows components
 - restarting
 - 127
 - starting
 - 127
 - stopping
 - 127