HCLSoftware

HCL iAutomate

KRS Guide

Version 6.5

The data contained in this document shall not be duplicated, used, or disclosed in whole or in part for any purpose. If a contract is awarded to chosen parties because of or in connection with the submission of this data, the client or prospective client shall have the right to duplicate, use, or disclose this data to the extent provided in the contract. This restriction does not limit the client's or prospective client's right to use the information contained in the data if it is obtained from another source without restriction. The data subject to this restriction is contained in all marked sheets. HCL has more than 200 offices worldwide. Addresses, phone numbers, and fax numbers are listed on the HCL website at www.hcltechsw.com.

Copyright © 2025 HCL Technologies Limited.

Table of Contents

1 Preface				
6				
6				
6				
6				
8				
10				
· · · ·				

List of figures

Figure 1 – Login to KRS Portal	8
Figure 2 – Change Super Admin Authentication Type	8
Figure 3 – LDAP Authentication Type	9
Figure 4 – SAML Authentication Type	9
Figure 5 – Encryption Key Rotation	10
Figure 6 – Encryption Key Rotation	11

List of Tables

Table	1 - Conventions	6
Iable	T - COLLACTIFICATION	 ٠.

Document Revision History

This guide is updated with each release of the product or when necessary.

This table provides the revision history of this KRS Guide.

Version No.	Version Date	
October, 2023	HCL iAutomate_6.3 KRS Guide	
December, 2023	HCL iAutomate_6.3.2 KRS Guide	
June, 2024	HCL iAutomate_6.4 KRS Guide	
August, 2024	HCL iAutomate_6.4.1 KRS Guide	
November, 2024	HCL iAutomate_6.4.2 KRS Guide	
January, 2025	HCL iAutomate_6.5 KRS Guide	

1 Preface

This section provides information about the KRS Guide and includes the following topics.

- Intended Audience
- About This Guide
- Related Documents
- <u>Conventions</u>

1.1 Intended Audience

This information is intended for administrators responsible for configuring automate.

1.2 About this Guide

This guide provides information regarding KRS in which users can change root user password for different authentication types and rotate encryption key after KRS login.

1.3 Related Documents

The following documents can be referenced in addition to this guide for further information on the automate platform.

- iAutomate Installation Guide
- iAutomate Introduction Guide
- iAutomate Troubleshooting Guide

1.4 Conventions

The following typographic conventions are used in this document:

	Table 1 - Conventions
Convention	Element

Convention	Element
Boldface	Indicates graphical user interface elements associated with an action, or terms
	defined in text or the glossary
<u>Underlined blue</u>	Indicates cross-reference and links
Italic	Indicates document titles, occasional emphasis, or glossary terms
Courier New	Indicates commands within a paragraph, URLs, code in examples, and paths
(Font)	including onscreen text and text input from users
Numbered lists	Indicates steps in a procedure to be followed in a sequence
Bulleted lists	Indicates a list of items that is not necessarily meant to be followed in a sequence

2 iAutomate

2.1 Introduction

This document provides all the changes the user can perform post login in KRS service.

The Below operations can be performed by the user in different ways: -

- 1. KRS Service Login
- 2. Change Root Authentication Type/Super Admin to login with Form Based or LDAP or SAML. and generate new passwords for root user when user authentication type is Form based.
- 3. Rotate Encryption Key

No changes are required in installers, root user created by the installer will be having the authentication type as Form Based by default.

2.2 UI and component changes

2.2.1 Login in KRS Service

If you are logging into KRS web application for the first time, to perform configuration, the user must have login credentials for application service account.

- 1. Launch a web browser and enter KRS web application URL.
- 2. On the login page, the KRS Login Page appears.
- 3. Select Domain account or Local Administrator from the dropdown.
- 4. Enter "Domain/Local" account through which KRS site is hosted.

If user selects 'Local Administrator' from dropdown, enter ".\" in the Domain field.

5. Enter Username and Password for the account from which KRS site is hosted.




Figure 1 – Login to KRS Portal

2.2.2 Change Super Admin Authentication Type

You may change Super Admin authentication type to login with Form Based or LDAP or SAML and generate a new password for super admin when user authentication type is Form based.

Select **Home** from the menu bar. This page is used to update the authentication type for Root/Super Admin users. However, the default Authentication Type is set to be Form Based.



Figure 2 – Change Super Admin Authentication Type

User can change the Authentication Type in following ways:

From Based Authentication Type:

- 1. Select Form Based on dropdown of Authentication Type.
- 2. Enter Root Email (account) for which the user wants to generate new passwords.
- 3. Add License Key, key which is used while KRS configuration for root/Super Admin login.
- 4. Select checkbox Agree to Terms if user agrees to the terms.

5. Click on the button Generate New Password to generate a new password for the account.

LDAP Authentication Type:




Figure 3 – LDAP Authentication Type

- 1. Select LDAP on dropdown of Authentication Type.
- 2. Enter AD Email (HCL account) to which user must give root/super admin privileges.
- 3. Enter LDAP URL.
- 4. Enter LDAP/Domain Username.
- 5. Check 'Is SSL Required', if required.
- 6. Add License Key, key which is used while KRS configuration for root/super admin login.
- 7. Select checkbox Agree to Terms if user agrees to the terms.

SAML Authentication Type:




Figure 4 – SAML Authentication Type

- 1. Select SAML on dropdown of Authentication Type.
- 2. Enter Email.
- 3. Enter ID.

- 4. Enter URL
- 5. Enter Name Id.
- 6. Enter Tool
- 7. Enter Logout URL.
- 8. Add License Key, key which is used while KRS configuration for root/superadmin login.
- 9. Select checkbox Agree to Terms if user agrees to the terms.
- 10. On clicking the Update button, license key will be validated.

2.2.3 Rotate Encryption Key

This page is used to rotate encryption keys.

- 1. Select Rotate Encryption Key tab from the menu bar.
- 2. Enter the License key and click Rotate Encryption Key button.



2.2.4 Configure Whitesource URL

This following page is used for whitelisting source URLs. Click Configure Whitelist URL tab from the menu bar. Now click Add new record to add a new URL to the list. Click the Edit button to modify any existing URLs. If you want to remove a URL completely, click the Delete button.



Figure 6 – Encryption Key Rotation

HCLSoftware